

AD-A104 933

SYSTEMS TECHNOLOGY INC HANTHORNE CA

F/G 6/6

USER'S GUIDE TO BIODYN-801 AN INTERACTIVE SOFTWARE PACKAGE FOR --ETC(U)

JUL 81 S A RIEDEL, R E MAGDALENO, H R JEX

F33615-79-C-0519

UNCLASSIFIED

STI-TR-1146-1

AFAMRL-TR-81-59

NL

TOP
SECRET

END
DATE
FILMED
10 81
DTIC

LEVEL II

12

AFAMRL-TR-81-59

AD A104933



**USER'S GUIDE TO BIODYN-80;
AN INTERACTIVE SOFTWARE PACKAGE FOR
MODELING BIODYNAMIC FEEDTHROUGH TO
A PILOT'S HANDS, HEAD, AND EYES**

**SUSAN A. RIEDEL
RAYMOND E. MAGDALENO
HENRY R. JEX**

**SYSTEMS TECHNOLOGY, INC.
13766 SOUTH HAWTHORNE BOULEVARD
HAWTHORNE CALIFORNIA 90250**

JULY 1981

**DTIC
ELECTE
OCT 2 1981
H**

Approved for public release; distribution unlimited.

**AIR FORCE AEROSPACE MEDICAL RESEARCH LABORATORY
AEROSPACE MEDICAL DIVISION
AIR FORCE SYSTEMS COMMAND
WRIGHT-PATTERSON AFB OH 45433**

81 10 2 088

ONE FILE COPY

NOTICES

When US Government drawings, specifications, or other data are used for any purpose other than a definitely related Government procurement operation, the Government thereby incurs no responsibility nor any obligation whatsoever, and the fact that the Government may have formulated, furnished, or in any way supplied the said drawings, specifications, or other data, is not to be regarded by implication or otherwise, as in any manner licensing the holder or any other person or corporation, or conveying any rights or permission to manufacture, use, or sell any patented invention that may in any way be related thereto.

Please do not request copies of this report from Air Force Aerospace Medical Research Laboratory. Additional copies may be purchased from:

National Technical Information Service
5285 Port Royal Road
Springfield, Virginia 22161

Federal Government agencies and their contractors registered with Defense Documentation Center should direct requests for copies of this report to:

Defense Documentation Center
Cameron Station
Alexandria, Virginia 22314

TECHNICAL REVIEW AND APPROVAL

AFAMRL-TR-81-59

This report has been reviewed by the Office of Public Affairs (PA) and is releasable to the National Technical Information Service (NTIS). At NTIS, it will be available to the general public, including foreign nations.

This technical report has been reviewed and is approved for publication.

FOR THE COMMANDER



HENNING E. VON GIERKE
Director
Biodynamics and Bioengineering Division
Air Force Aerospace Medical Research Laboratory

SECURITY CLASSIFICATION OF THIS PAGE (When Data Entered)

REPORT DOCUMENTATION PAGE		READ INSTRUCTIONS BEFORE COMPLETING FORM
1. REPORT NUMBER AFAMRL TR-81-59	2. GOVT ACCESSION NO. AD-A104933	3. RECIPIENT'S CATALOG NUMBER
4. TITLE (and SUBTITLE) USER'S GUIDE TO BIODYN-80; AN INTERACTIVE SOFTWARE PACKAGE FOR MODELING BIODYNAMIC FEEDTHROUGH TO A PILOT'S HANDS, HEAD, AND EYES		5. TYPE OF REPORT & PERIOD COVERED Final Report 1779 to 11/80
6. AUTHOR(s) Susan A. Riedel Raymond E. Magdaleno Henry R. Jex		7. PERFORMING ORG. REPORT NUMBER TR-1146-1
8. CONTRACT OR GRANT NUMBER(s)		
9. PERFORMING ORGANIZATION NAME AND ADDRESS Systems Technology, Inc. 13766 S. Hawthorne Blvd. Hawthorne CA 90250		10. PROGRAM ELEMENT, PROJECT, TASK AREA & WORK UNIT NUMBERS 61102F 2312-V3-20
11. CONTROLLING OFFICE NAME AND ADDRESS Air Force Aerospace Medical Research Laboratory, Aerospace Medical Division, Air Force Systems Command, Wright-Patterson AFB OH 45433		12. REPORT DATE July 1981
14. MONITORING AGENCY NAME & ADDRESS (if different from Controlling Office)		13. NUMBER OF PAGES 73
		15. SECURITY CLASS. (of this report) Unclassified
		15a. DECLASSIFICATION/DOWNGRADING SCHEDULE
16. DISTRIBUTION STATEMENT (of this Report) Approved for public release; distribution unlimited.		
17. DISTRIBUTION STATEMENT (of the abstract entered in Block 20, if different from Report)		
18. SUPPLEMENTARY NOTES		
19. KEY WORDS (Continue on reverse side if necessary and identify by block number) <div style="display: flex; justify-content: space-between;"> <div> Biodynamics Whole-body Vibration Visual Performance Human Transmissability </div> <div> Control Performance Man/Machine Interface Computer Program: BIODYN-80 </div> </div>		
20. ABSTRACT (Continue on reverse side if necessary and identify by block number) <p>This is the User's Manual for BIODYN-80, an interactive computer program for solving the dynamic motion response of seated aircrew (pilots or equipment operators) working in a biodynamic environment (such as vibration or changing levels of acceleration in aircraft, surface vehicles, or motion simulators). The multi-degree-of-freedom, lumped-parameter model includes elements for: pelvis, torso, neck, head, eyes, upper and lower arms, hand-grip and control stick (center-stick with arm rest). An active 21-parameter neuromuscular system is operable with either the limb or head control. The eye's image</p>		

DD FORM 1 JAN 73 1473 EDITION OF 1 NOV 65 IS OBSOLETE

SECURITY CLASSIFICATION OF THIS PAGE (When Data Entered)

AD-A104933

304

20. ABSTRACT (continued)

motion dynamics include a 13-parameter model for the fixation and vestibulo-ocular reflexes. The nonlinear equations of motion of the body's main elements are linearized about a general set of body-limb-head postures, ranging from prone, to erect, to supine. Inputs are vertical or fore-aft accelerations of the seat, while a wide variety of outputs are available, including motions of the shoulder, head, eyes, arm, hand, or control stick. Typical parameter ranges and sources are given, along with two "typical" sets: a seated-pilot with center-stick, and a seated crewman with hands in lap.

The program can be run in a mode interactive with the user, or in a batch mode. The program helps the user load the necessary parameters, and offers a "quick-look" printer plot of the resulting frequency responses, in standard Bode-plot forms. The program also can produce biomechanical transmissability files needed for use in the Air Force's PIVIB program for tracking performance estimation.

Procedures and examples are given for both a Cyber 175 version available on "INTERCOM" for Wright-Patterson Air Force Base users, and a PDP-10 version, available on the Tymshare national computer network for other users.

PREFACE

This report was prepared by Systems Technology, Inc., Hawthorne, California, under Contract F33615-79-C-0519, for the Air Force Aerospace Medical Research Laboratory (AFAMRL). Mr. Charles Harmon, Biodynamic Effects Branch of the Biodynamics and Bioengineering Division, served as the technical monitor for AFAMRL in support of Project 2312-V3-20, "Man-Machine Interface Model."

Accession For	
NTIS GRA&I	<input checked="checked" type="checkbox"/>
DTIC TAB	<input type="checkbox"/>
Unannounced	<input type="checkbox"/>
Justification	
By	
Distribution/	
Availability Codes	
Date	
A	

TABLE OF CONTENTS

	<u>Page</u>
INTRODUCTION.....	4
A Scope.....	4
B Background.....	4
C Applications.....	5
SOFTWARE OVERVIEW.....	6
MODEL DESCRIPTION.....	10
A Biomechanical Model.....	10
B Limb Neuromuscular Model.....	12
C Neck/Head/Eye Models.....	12
USING BIODYN-80.....	17
A CREATE.....	17
B BIODYN.....	27
C Plot.....	28
D Interface with PIVIB.....	28
E For Assistance.....	35
APPENDIX A DEFINITION OF PARAMETERS, SYMBOLS, RANGES AND TYPICAL VALUES.....	36
APPENDIX B DEFINITION OF FORCING FUNCTION AND RESPONSE VARIABLES.....	45
APPENDIX C EQUATIONS OF MOTION.....	49
APPENDIX D TYMSHARE EXAMPLE PROBLEM.....	57
APPENDIX E INTERCOM EXAMPLE PROBLEM.....	66
REFERENCES.....	69

LIST OF ILLUSTRATIONS

<u>Figure</u>	<u>Page</u>
1 Overview of BIODYN-80.....	7
2 BIODYN-80 Flow Chart.....	8
3 Main Biomechanical Elements.....	11
4 Linearized Limb Neuromuscular System.....	13
5 Simplified Head Pointing Neuromuscular System.....	14
6 Block Diagram for Head, Eye, Vestibular Models and Display Kinematics.....	15
7 Example Long Format File Listing.....	20
8 Example Short Format PARAMETER File Listing.....	22
9 Format for BIODYN-80 Transfer Function Printouts.....	29
10 Format Used for BIODYN-80 TAPE19 File of Transfer Functions.....	30
11 Example Output from Plot.....	31
12 BIODYN-80 Transfer Functions Which May Be Used as PIVIB Input.....	34

LIST OF TABLES

<u>Table</u>		
1 Parameter and Symbol Definitions, Ranges, and Typical Values.....		36
2 Parameter File Structure (Short Format).....		43
3 Input (Forcing Function) Variables.....		45
4 Output (Response) Variables.....		46

INTRODUCTION

A. SCOPE

BIODYN-80 is a versatile computational tool used to determine transmissibilities (transfer functions) between vertical and/or fore-aft vibrational inputs and important biodynamic outputs, such as motions of the torso, head, eyes, arms or hands. The program scenario assumes a seated pilot, gripping an arbitrary-angle stick and viewing a display, possibly engaged in a tracking task. The physical model uses an "isomorphic," (lumped parameter,) approach to represent the relevant portions of the whole-body torso, limbs and head, as well as postural compliances among the joints. The implementation of this model includes a chain of interacting parallel and serial second-order elements, with neuromuscular and other force feedbacks at the arm or head. The resulting equations are in "second-order element" matrix form and apply to a wide range of seated postures. A separate input file, which describes the particular set of parameters to be used, is created by the user (usually by modifying one of a cataloged set). This file is incorporated in the matrix to produce linearized coefficients for perturbations about the selected equilibrium posture. A variety of outputs and inputs can be specified to evaluate the desired transmissibility transfer functions, and these are written to a file in formatted form for plotting or use in other programs. On-line, printer-drawn frequency response plots (Bode format) are available to aid in interactive user-computer operations, or to screen significant results from batch runs.

B. BACKGROUND

BIODYN-80 is one result of a several year small-scale development effort, reported in detail in References 1-6. It is based on vibration

measurements made at the Aerospace Medical Research Lab/Biodynamics Division (AMRL/BB) and elsewhere. Most of the torso, limb and stick model elements are based on independent vibration measurements (e.g., Reference 5), and the neck, head and eye effects show promising correlations with the few available measurements on image motion effects (Reference 6). However, many aspects remain to be explored, validated or upgraded as more experiments are run and interpreted via BIODYN-80.

C. APPLICATIONS

The possible applications of this program are many. It should be used in the early stages of experimental design for determining the optimal locations for vibration measurements and/or selection of frequencies. It can also be used by development engineers for solving practical pilot-vehicle interface design problems such as pilot-induced oscillations and for optimizing design alternatives such as seat location, orientation and suspension parameters. Flight control system designers can make use of BIODYN-80 output in optimizing vehicle/ aircrew ride qualities and visual performance effects, possibly incorporating anti-vibration devices to improve the design.

One further application of BIODYN-80 deserves special mention. Its vibration-input to biodynamic parameter-output transfer functions are ideally suited as input to PIVIB, another software package which relates pilot tracking performance to the vibration environment (Reference 7). PIVIB accepts biomechanical transfer functions in the format created by BIODYN-80. The details of the BIODYN-80/PIVIB interface will be found in a later section.

The remainder of this report details the use of BIODYN-80, and describes the model and the equations comprising it. Detailed instructions for the creation of the required input files, and a complete example problem are also included.

SOFTWARE OVERVIEW

Figure 1 is a functional block diagram description of the elements in BIODYN and its interface with PIVIB. The BIODYN-80 package is composed of three programs. The first, called CREATE,* interactively sets up the two input files used by BIODYN. The second program called BIODYN, is the actual "number cruncher," which structures and solves the biomechanical equations and computes the desired transfer functions. The third program called PLOT, accepts the file of BIODYN transfer functions, prints selected ones in a form readily comprehended by the user, and prepares "quick plot" Bode plots on the line printer, to facilitate a visual interpretation of the transfer function information. Both BIODYN and PLOT are designed primarily as batch programs while, CREATE permits conversational user interaction in structuring input data.

A subsequent link in this series of programs is PIVIB. It is a large batch program with three modules. The first, BDMOD, computes the response behavior of the various biomechanical subsystems. The second, PVMOD, uses the results of BDMOD and the BBN optimal control model to estimate pilot tracking performance within the vibration environment. The final module, VEXEC, provides the top level communication interface between BDMOD and PVMOD, and performs no actual computation. The BDMOD module expects biodynamic transfer functions in a format generated by BIODYN. Only the relationships of BIODYN-80 to PIVIB are described herein, because PIVIB is run separately and has its own User's Manual (Reference 7).

Figure 2 presents a flow chart covering the use of BIODYN and PIVIB in a given session. The detailed description of the various steps for BIODYN is found in Section D. Note that the flow of execution can be

*The CREATE program should not be confused with INTERCOM's EDITOR subcommand CREATE; it has been given the permanent file name EXECRT to distinguish it from the latter.




Figure 1 Overview of BIODYN-80




Figure 2 BIODYN-80 Flow Chart

used to solve a single problem, by submitting a single batch request, or to iterate on a design by submitting a number of batch requests using the same CHOICES file and slightly altered PARAMETER files (heavy lines in Figure 2).

BIODYN-80 uses three separate files in performing its computations. The PARAMETER file contains the set of 96 parameters used to define the specific pilot/posture/display/vibration characteristics. Appendix A contains a complete description of each parameter, including definition, mnemonic, nominal value, recommended range of values and reference (where available). CREATE is used to assemble this file and can modify an existing file or produce an entirely new file. The CHOICES file contains the list of desired transfer functions to be computed and output by BIODYN, as well as directives for producing the line printer Bode plots. Again, this CHOICES file is assembled by CREATE. Finally, the TF file is used to store the resulting transfer functions output by BIODYN, and is read by the PLOT routine for generating Bode plots.

PIVIB employs a single large file to direct its flow of execution. This file defines the vibration environment, biomechanical transfer functions, tracking dynamics, tracking performance requirements, and pilot limitations (bandwidths, time delays, etc.). Currently, this file is assembled in the editor, using output from BIODYN-80 if desired.

BIODYN-80 and each of its predecessors were developed on the Tymshare, Inc., PDP-10 computers. BIODYN-80 has been adapted to the CDC "Intercom" System on the CDC 6600 or CYBER 175 at WPAFB in order to increase its availability to Air Force users, and to interact with PIVIB, which is also operable on the WPAFB CDC computer. The details of this manual will address its use on the CDC machine; an example of a Tymshare session is given in Appendix D. Throughout the manual, however, it is assumed that the user is familiar with the WPAFB CYBER 175, and in particular has experience with the INTERCOM operating system. If not, the user should read References 8 and 9 first.

MODEL DESCRIPTION


Three distinct subsystem models are included in BIODYN-80. They are described individually below.

A. BIOMECHANICAL MODEL


Figure 3 (updated from Figure 2 of Reference 3) presents the biomechanical model and defines many of the necessary parameters that describe the nominal (or trim) situation. It utilizes an "isomorphic," or body-mimicking representation, of the major body segments in their orientations, simplified to a minimum number of lumped parameter equivalents. The biomechanical features include:

- Semisupine torso; sliding hip plus rocking chest supported on a compliant buttocks/seat.
- Head bobbing on an articulated neck with passive compliance, or active neuromuscular system.
- Upper arm and forearm links plus grip-interface compliance, driven by an active neuromuscular system.
- Arm-rest restraints (optional).
- Stick "feel system" dynamics from zero to infinite stiffness, and any angle of stick or grip.

The simplified torso model was derived to describe the dominant motions of the head and arm elements; the "pin joint" node between upper and lower torso segments is not meant to represent any physical feature. In practice, the masses and inertias are obtained from tabulated biomechanical and anthropometric data for the appropriate sized person (e.g., Reference 11), the postural angles are based on the actual situation (preferably via a side-view photo), and the spring forces and damping coefficients are fitted to data or taken from other sources (e.g., References 3 and 12).




a) Basic Elements



b) Body Parameters

Note:
 $L_1 = L_a + L_b$
 $L_2 = L_d + L_e$
 $\theta_r = 180^\circ - \theta_E$
 $\theta_a = 90^\circ - \theta_E + \theta_i$



c) Arm Rest Detail

Figure 3 Main Biomechanical Elements

B. LIMB NEUROMUSCULAR MODEL

The active neuromuscular system noted on Figure 3 is a schematic representation of the net effect of complex agonist/antagonist muscle pairs controlling the upper arm or head based on the work summarized in Reference 10. An "NM switch" is defined in the PARAMETER file which causes this neuromuscular model to control the limb ($NM = 0$) or the head ($NM = 1$). A linearized representation of the limb neuromuscular model is shown in Figure 4, while the head neuromuscular model is depicted in Figure 5. This model relates the action of the muscle pairs to the effective (spindle) sensors of muscle length and force as well as proprioception from the stick grip interface (in the case of the limb neuromuscular model) or the head-neck interface (in the case of the head neuromuscular model), thus closing the receptor-CNS-effector loop.

Unless neuromuscular properties are being investigated, it is recommended that the typical values of the parameters shown in Table A-1 be used. These are representative of a normal person's arm-hand or head-neck system, and generally yield reasonably damped neuromuscular servo properties. The neuromuscular parameters listed in Appendix A are characteristic of the largest muscles in the body (e.g., the legs), but experience has shown that the dynamic properties (torque/inertia ratios, damping ratios, natural frequencies, etc.) are about the same for all postural muscle pairs. Here, an empirical scale factor S (> 1.0) is used to scale the normalized muscle to a particular configuration, as though the muscle acted normal to the upper arm c.g. A more detailed description of the neuromuscular model is found in Reference 10.

C. NECK/HEAD/EYE MODELS

Figure 6 illustrates the basic elements involved in the neck/head/eye model. Details involving validation and example use of this subsystem model are found in Reference 6. The task is to keep the eye fixated on the target, i.e., null the relative eye (point of regard) deviation (RED) at the display. The moving base can produce image error disturbances, both from induced head rotation and translation as well as





Figure 4 Linearized Limb Neuromuscular System (When the Option NM = 0)



Notes:

When $NM=1$, this simplified NM system is connected to the head to maintain head pointing at the vibrating target. The values of the parameters F_A , K_{1c} , K_a , etc. are different between the limb case ($NM=0$) and head case ($NM=1$)

Figure 5 Simplified Head Pointing Neuromuscular System
(When Option NM = 1)




Figure 6 Block Diagram for Head, Eye, Vestibular Models and Display Kinematics

target motions. The "vestibulo-ocular reflex" is a "crossfeed" (or "feedforward") that rotates the eye oppositely to the head to compensate for head rotation, i.e., to maintain approximate inertial eye fixation.

The "Fixation Reflex" or feedback tracking loop involves the subject's efforts to null the image error θ_I by compensatory eye movements. The "Target Pursuit" path (shown dashed) models the subject's "feedforward" operations on the perceived absolute target motions in inertial space (as distinct from the image error motions). For highly predictable and perceivable target motions the Target Pursuit path is capable of greatly reducing the image errors, but it is not involved in most vibration cases because of insufficient bandwidth.

The linearized model formulation assumes that the target remains within the foveal area (3-4 deg field), and that angular velocities are small (i.e., less than 20 deg/sec) such that saccades are rare and can be ignored. Additionally, the vibration-induced motions will always be small enough to permit linearization of all angular functions and allow a quasi-linear representation of the dynamic elements about each "operating point" (posture, view geometry, frequency). The operating point angles can have any values within human limits for a seated pilot or crewman.

The three subsystem models described above contain parameters which must be assigned values via the PARAMETER file, in order to describe the desired problem to BIODYN. These parameters are defined in Appendix A. The available input (forcing function) variables and output (response) variables are given in Appendix B. Two different input deflection variables are available for the x and z axes. BZP and BXP should be used when absolute outputs (referenced to inertial space) are desired; DZP and DXP are used when outputs relative to the moving platform are desired. The equations of motion are in Appendix C. Background on their derivation and development are given in a series of prior reports (References 1-3, 6, 10).

USING BIODYN-80

Three job steps are required for a complete run of BIODYN-80. The CREATE program is used interactively via a remote terminal, to assemble the PARAMETER and CHOICES files. These files are then read by BIODYN and the transfer functions computed, stored on the TF file, and listed at a line printer. The TF file is in turn read by the PLOT program to produce any Bode plots desired. Each of these steps is described in detail. Note that all user interaction with the computer assumes the user is logged in to CDC's INTERCOM. It is assumed that the user has access to Intercom set "AFML" where the program and its files reside. For other setname groups, please consult your Computer Center Representative to get on the AFML list, or for instructions on how to use a "modified job stream listing" (Reference 8).

A. CREATE

Because of the large number of parameters required by BIODYN-80, it was decided that a dedicated interactive "editor" for creating parameter files was needed to produce rational, error-free input files, and thereby avoid aborting during the subsequent, and expensive, batch run of BIODYN (for example, due to a missing decimal point). Furthermore, this approach allows the maintenance of a "catalog" of PARAMETER files for various postures and situations, from which the most appropriate one can be easily selected and modified for a particular situation. The CREATE program serves in this regard by allowing a user to interactively assemble new parameter files or modify existing ones. CREATE also performs various data checks and identifies common parameter entry errors. This section details the use of the CREATE program.

1. Entering CREATE

CREATE makes use of five files, as defined by the PROGRAM card:

TAPE4 = INPUT file (the user's terminal)

TAPE5 = OUTPUT file (the user's terminal)
 TAPE7 = CHOICES file (if new one is created)
 TAPE8 = PARAMETER file (new or modified)
 TAPE20 = PARAMETER file (existing)

The PROGRAM card automatically assigns the INPUT and OUTPUT files to the appropriate tape units. If an existing PARAMETER file is to be accessed, it must be assigned prior to executing CREATE. The job stream to be input by the user looks like this (detailed examples are given later, in Appendices D and E):

REQUEST,TAPE7,*PF	(pfn ₁ is the PARAMETER file name
REQUEST,TAPE8,*PF	selected by the user from the
ATTACH,TAPE20,pfn ₁	permanent file catalog within
ATTACH,EXECRT	the setname AFML group)
EXECRT	

Now the user is at the entry level of CREATE. The first issue addressed is creating the PARAMETER file, or modifying an existing PARAMETER file. The computer's first prompt

NEW FILE?

asks the user to identify which option is desired. Answers are YES or NO; any other response will cause the query to be repeated.

2. Modifying a PARAMETER File

If the answer is NO, the values stored on the file assigned to TAPE20 are read. The user may list those values by responding to the next prompt

LISTING DESIRED?

with YES. A NO response will skip over the listing option. Any other response will cause repeat of the question. The listing produced can either be long or short. The long listing provides parameter definition, mnemonic, units and current value, while the short listing prints only values, grouped according to each element (see Table A-2, Appendix A). Examples of each are given in Figures 7 and 8, respectively.

Response to the prompt:

(LONG OR (SHORT LISTING?

determines which listing to generate. A response other than LO or SH will cause repeat of the question.

Values are now ready for change, as indicated by the message:

INPUT MNEMONIC (5 CHARS) AND VALUE FOR EACH CHANGE,
TO EXIT, TYPE XXX.

To change any desired parameter value, its mnemonic from the second column of the definitions in Appendix A is input. Mnemonic must be left justified within a 5 character field followed by a comma, followed by the new value. The mnemonic is then checked against the internal list of permissible mnemonics; e.g., if ABDCE is not found, the message:

MNEMONIC ABCDE NOT PERMISSIBLE. PLEASE REINPUT.

appears and the user should try again. Likely errors include typos, and forgetting to pad the 5 character field with trailing blanks.

Once a correct mnemonic is identified, its new value is compared with the recommended range of values for that parameter. If the value is not within that range, a warning message appears:

WARNING - RECOMMENDED RANGE FOR THIS PARAMETER IS
0.5 TO 3.5 GS
DO YOU WANT TO CHANGE THE VALUE?

STD CREWMAN, HANDS ON KNEES

PARAMETER DEFINITION	MNEMONIC	UNITS	VALUE
LOWER BODY MASS	XMB	KG	14.0000
L. BODY SEAT CUSHION DAMPER	BB	N/M/S	315.000
L. BODY SEAT CUSHION STIFFNESS	XKB	N/M	49360.0
SERIES SPRING GRAD.-LOWER BODY	GK1	N/M	119320.
SEAT TILT ANGLE	THL	DEG	13.0000
TRIM VERTICAL ACCEL.	G	M/S2	9.80000
TORSO MASS	XMT	KG	18.0000
TORSO INERTIA	ZIT	KGM2	.800000
TORSO DAMPING	BTB	NM/R/S	40.0000
TORSO STIFFNESS	XKTB	NM/R	500.000
ANGLE OF XLT FROM VERTICAL	THT	DEG	-15.0000
TORSO CG TO HIPS PIVOT LENGTH	XLT	M	.150000
ANGLE OF XLTN	THTN	DEG	-5.00000
TORSO CG TO NECK/TORSO PIVOT	XLTN	M	.300000
ANGLE OF XLS	THS	DEG	-5.00000
TORSO CG TO SHOULDER LENGTH	XLS	M	.300000
NECK MASS	XMN	KG	1.24000
NECK INERTIA	ZIN	KGM2	.240000E-02
NECK/TORSO DAMPER	BNT	NM/R/S	.100000
NECK/TORSO STIFFNESS	XKNT	NM/R	50.0000
ANGLE OF XIN	THN	DEG	-30.0000
NECK LENGTH	XLN	M	.124440
NECK CG TO NECK/TORSO PIVOT	XLN1	M	.622200E-01
HEAD MASS	XMH	KG	3.10000
HEAD INERTIA	ZIH	KGM2	.303000E-01
HEAD/NECK DAMPER	BHN	NM/R/S	.126000
HEAD/NECK STIFFNESS	XKHN	NM/R	15.0000
HEAD/NECK COMPLIANCE	CH	-	1.00000
ANGLE OF XLH	TH	DEG	60.0000
HEAD CG TO HEAD/NECK PIVOT LEN	XLH	M	.250000E-01
LINE OF SIGHT ANGLE	THV	DEG	-30.0000
VIEWING DISTANCE	VD	M	.685300
UPPER ARM MASS	XM1	KG	1.37200
UPPER ARM INERTIA	Z1	KGM2	.120000E-01
UPPER ARM ANGLE	T1	DEG	15.0000
UPPER ARM LENGTH	D1	M	.290000
UPPER ARM CG	R1	M/M	.440000
LOWER ARM MASS	XM2	KG	1.01700
LOWER ARM INERTIA	Z2	KGM2	.152000E-01
ELBOW ANGLE	TE	DEG	115.000
LOWER ARM LENGTH	D2	M	.305000
LOWER ARM CG	R2	M/M	.500000
GRIP INTERFACE ANGLE	TIJ	DEG	0.
GRIP INTERFACE TIME CONSTANT	TIF	S	.100000
GRIP INTERFACE COMPLIANCE	CI	M/N	1.00000

(continued)

Figure 7 Example Long Format File Listing

ARM REST DAMPER	XMS	KG	4.00000
ARM REST DAMPER	BS	N/M/S	240.000
ARM REST DAMPER	XKS	N/M	10000.0
ARM REST DAMPER PARAMETER	CKS	-	1.00000
ARM REST DAMPER SENSITIVITY TO NX	SX	N/G	0.
ARM REST DAMPER SENSITIVITY TO NZ	SZ	N/G	0.
ARM REST DAMPER	THC	DEG	90.0000
ARM REST DAMPER	XLC	M	.550000
ARM REST DAMPER SCALE FACTOR	XKSC	/M	.100000E-01
ARM REST DAMPER (NORMAL)	BAR	N/M/S	0.
ARM REST STIFFNESS (NORMAL)	XKAR	N/M	0.
ARM REST DAMPER (TANG)	BAT	N/M/S	0.
ARM REST STIFFNESS (TANG)	XKAT	N/M	0.
ARM REST ARM REST DISTANCE	XLER	M	0.
ARM REST WEIGHT ON ARM REST	ARMR	-	0.
ARM REST LENGTH FOR CENTRAL AND F.A.D.	NM	-	0.
ARM REST LENGTH FOR MUSCLE ELEMENTS	SI	-	50.0000
ARM REST LENGTH	ICC	S	.909000E-01
ARM REST LENGTH DELAY	ICS	S	.890000E-01
ARM REST LENGTH	XKAA	N/M	1.00000
ARM REST LENGTH	ZA	-	.800000
ARM REST FREQUENCY IN F.A.D.	WA	R/S	16.0000
ARM REST LENGTH IN F.A.D.	TAA	S	0.
ARM REST DAMPER	BM	N/M/S	1.00000
ARM REST D.A.R. SYSTEM	XKM	N/M	2.00000
SERIES PLANT ELEMENT DAMPER	BE	N/M/S	2.43000
SERIES PLANT ELEMENT GRAD	XKE	N/M	40.0000
ARM REST DAMPER	BT	N/M/S	0.
ARM REST LENGTH	XKT	N/M	80.0000
ARM REST LENGTH GAIN	XKSP	N/M	5.00000
ARM REST LENGTH TIME CONSTANT	TSP	S	.909000E-01
ARM REST LENGTH TIME CONSTANT	TPS	S	0.
ARM REST LENGTH TIME CONSTANT	TSS	S	0.
ARM REST LENGTH GAIN	XKG	N/M	.500000
ARM REST LENGTH TIME CONSTANT	TG	S	.550000E-01
ARM REST LENGTH TIME CONSTANT	TZ	S	0.
ARM REST LENGTH TIME CONSTANT	TP	S	0.
ARM REST LENGTH GAIN	XKDE	R/R	7.07750
ARM REST LENGTH GAIN	XKRE	R/R/S	0.
ARM REST LENGTH TIME CONSTANT	TV	S	.450000E-01
ARM REST LENGTH TIME CONSTANT	ALPHA	R/S	.300000
ARM REST LENGTH TIME CONSTANT	XKP	R/S	0.
ARM REST LENGTH TIME CONSTANT	XKIE	-	.670000
ARM REST LENGTH TIME CONSTANT	XKVS	-	.100000
ARM REST LENGTH TIME CONSTANT	TC2	S	.100000E-01
ARM REST LENGTH TIME CONSTANT	TEM	S	.100000
ARM REST LENGTH TIME CONSTANT	FLM	S	.125000E-01
ARM REST LENGTH TIME CONSTANT	QE	-	1.00000
ARM REST LENGTH TIME CONSTANT	ZE	-	.650000
ARM REST LENGTH TIME CONSTANT	WE	R/S	314.230

Figure 7 (Concluded)

PARAMETERS FOR:

SEATED CREWMAN - VIEWING DISTANCE = 9 CM

LOWER BODY

14.000	315.00	49360.	.11932E+06	13.000	9.8000
--------	--------	--------	------------	--------	--------

TORSO

18.000	.80000	40.000	500.00		
-15.000	.15000	-5.0000	.30000	-5.0000	.30000

NECK

1.2400	.24000E-02	.10000	50.000		
-30.000	.12444	.62220E-01			

HEAD/DISPLAY VIEWING

3.1000	.30300E-01	.12600	15.000	1.0000	
60.000	.25000E-01	-30.000	.90000E-01		

ARM (UPPER, LOWER)

1.3720	.12000E-01	15.000	.29000	.44000	
1.0170	.15200E-01	115.00	.30500	.50000	

GRIP INTERFACE

0.	.10000	1.0000			
----	--------	--------	--	--	--

STICK

4.0000	240.00	10000.	1.0000	0.	0.
90.000	.55000	.10000E-01			

ARM REST

0.	0.	0.	0.	0.	0.
----	----	----	----	----	----

NEUROMUSCULAR SYSTEM

0	50.000				
.20000E-01	.90900E-01	.89000E-01			
1.0000	.80000	16.000	0.		
1.0000	2.0000	2.4300	40.000	0.	80.000
5.0000	.90900E-01	0.	0.		
.50000	.55000E-01	0.	0.		

IMAGE FIXATION/VESTIBULO-OCULAR SERVO

7.0795	0.	.45000E-01	.30000	0.	
.67000	.10000	.10000E-01			
.10000	.12500E-01	1.0000	.65000	316.23	

Figure 8 Example Short Format PARAMETER File Listing

If a mistake has been made in typing the new value, a YES answer will allow retyping of both the mnemonic and its corrected value. If, however, the value is correct, even if out of range, a NO answer will cause the value to be stored as it stands. Any response other than YES or NO will cause the warning message to be repeated.

The range of parameters given in Appendix A is as wide as can be allowed for typical applications of BIODYN-80 (e.g., arm joint limits). Values outside this range are used at the user's risk, and precise postural angles for the given case should be carefully checked at this point. (It is good practice to check your lengths and angles by drawing a stick figure to scale, using the desired values.)

When all the desired changes have been made, an input of XXX causes control to leave the modify mode. An opportunity to change the case title is then presented as

TITLE IS STD CREWMAN, HANDS ON KNEES
CHANGE DESIRED?

A YES answer causes the message

NEW TITLE:

to appear and a new title (60 characters maximum) can be typed. A NO response skips this section; other responses cause the prompt to repeat.

After all desired changes have been made, the user is once again given the opportunity to list the file, using either the LONG or SHORT format, as described above. At this point the computer writes the new values to the PARAMETER output file, TAPE8.

3. Assembling a New PARAMETER File

If most of the parameters are new, then instead of modifying an existing file the initial prompt

NEW FILE?

is answered YES. Every parameter value must then be input. The message

INPUT VALUE FOR EACH MNEMONIC. FOR FURTHER EXPLANATION, TYPE?

initiates this process. For each parameter, the mnemonic is printed as, for example, Viewing Distance, VD:

VD =

and the value is accepted in floating point format. If the user is uncertain as to the range of appropriate values, an expanded prompt may be requested by typing "?". The expanded prompt for VD is, for example:

VD = ?

VD VIEWING DISTANCE
RECOMMENDED RANGE = 0.5 TO 3.0 M
VD =

the user can then enter the desired value.

As each value is read, it is checked against the recommended range of values, in order to weed out input errors due to wrong sign or incorrect decimal placement. If the value is not within range, the warning message given previously appears. The user always has the option of modifying or saving any value typed.

This process continues until all 26 parameters have been entered. The case title is then added as a response to

INPUT TITLE FOR THIS CASE:

At this point, a Long or Short format listing may be generated as discussed above. The file is then written by the computer to the PARAMETER file designated TAPE8.

4. Assembling the CHOICES File

The next section of CREATE is used to assemble a new CHOICES file which specifies the transfer functions to be output. Note that there is no provision for modifying an existing CHOICES file; any changes to an existing CHOICES file must be made by creating an entirely new file. The prompt

NEW CHOICES FILE?

has two responses: a NO allows the user to skip this entire section if an existing CHOICES file will be used as input to BIODYN; a YES response will cause prompting for the CHOICES file components as described below. Any other response will cause the prompt to be repeated.

A YES response to the next prompt

BIODYN TFS DESIRED FOR PIVIB?

will automatically generate the ten transfer functions to be included in the PIVIB input file. This is mandatory if interaction with PIVIB is anticipated. The response and forcing function variables involved are shown later, in Figure 12. A NO answer skips this section; other answers cause repeat of the question.

All other desired transfer functions are entered by the user in response to the following computer-specified format:

TRANSFER FUNCTION INPUT:
FIRST LINE - RESPONSE MNEMONIC, FORCING FUNCTION MNEMONIC
(AAA, AAA); ENTER XXX TO STOP
SECOND LINE - PLOTTING INFORMATION, 5 ITEMS:
BODE LOWER FREQ. LIMIT
BODE UPPER FREQ. LIMIT
BODE UPPER PHASE LIMIT (0. DEFAULTS TO 200.)
BODE LOWER PHASE LIMIT (0. DEFAULTS TO -400.)
LIST (1. TO LIST TABLE, 0. FOR NO LIST)
IF NO PLOT DESIRED, ENTER 0. FOR ALL ITEMS

Note that the parameters for each transfer function are entered on two consecutive lines, each item separated by a comma, each line followed by CR.

The mnemonics requested are three-character codes as defined in Appendix B. The program checks each mnemonic against the list of acceptable codes. If a match is not made, the error message

XYZ NOT PERMISSIBLE, PLEASE REINPUT.

is given and the entire first line must be retyped.

If Bode plots are desired, the frequency and phase limits must be entered; if not, zeros are assumed. The frequency limits must bound a frequency range of no more than 3 decades. If frequencies with an unacceptable range are entered, the message

MAX FREQUENCY RANGE IS 3 DECADES
PLEASE REINPUT ENTIRE LINE

appears and, all five items for that transfer function must be re-typed. The phase limits are unbounded, but entering zeros will cause default to +200.0 deg and -400.0 deg for the upper and lower limits, respectively. If a tabular listing, including frequency, amplitude, and phase at 20 increments/decade intervals is desired, a 1.0 should be entered as the fifth item; otherwise enter 0.0.

The CREATE program stops when an XXX is read in the CHOICES file section. The two files created must be saved as permanent files by giving the following INTERCOM commands:

CATALOG,TAPE7,pfn₂,RP=10
CATALOG,TAPE8,pfn₃,RP=10

where pfn₂ is a new (seven character) permanent file name assigned to the CHOICES file and pfn₃ is a new (seven character) permanent file name assigned to the PARAMETER file. The user is now ready to exercise BIODYN.

The user can interactively create a number of PARAMETER and CHOICES files, each uniquely named for subsequent use in the BIODYN program. In

most cases one same set of transfer function choices will be adequate for a variety of different parameter sets.

B. BIODYN

Because of memory size limitations presently imposed by the INTERCOM operating system, BIODYN must be run in the batch mode. A batch job can be submitted through INTERCOM using the following command sequence

```
EDITOR
CREATE,S
ABC,CM150000,STCSA.
ATTACH,TAPE7,pfn2.      User supplies desired
ATTACH,TAPE8,pfn3.      file name for each pfn
REQUEST,TAPE19,*FF.
ATTACH,EXEBIO.
EXEBIO(TAPE4,OUTPUT,TAPE7,TAPE8,TAPE19,TAPE21).
CATALOG,TAPE19,pfn4,RP=999.
*EOR
SAVE,GOBIO,NOSEQ
END
COMMAND = BATCH,GOBIO,INPUT,HERE
```

The first section of this batch request assigns the PARAMETER and CHOICES files produced by CREATE to the tape units which BIODYN reads. The BIODYN program is then retrieved and executed.

BIODYN first reads the PARAMETER file and uses it to set up the equations in the form

$$Ax = Bu$$

where x is a vector of response variables (currently dimensioned 48) and u is a vector of forcing function variables (dimensioned 9). The desired transfer functions (as listed in the CHOICES file) are then evaluated, using Cramer's rule and several advanced factorization algorithms in order to obtain the first- and second-order poles and zeros. These are all written to a file called TAPE19 (the TF file), as well as to the line printer (via the OUTPUT file). The format used by the program for

printing the transfer functions is shown in Figure 9, while the format for storing these transfer functions on TAPE19 is given in Figure 10.

The TF file (TAPE19) is used by the PLOT program for generating the quick-look Bode plots on the line printer. Thus, the last lines supplied by the user in the batch job stream "rewind" this file and assign it a permanent file name pfn_4 .

C. PLOT

The Bode plots, if desired, may be generated at the user's terminal or written to a local file for later examination, as the user wishes. The user's job stream looks like the following:

ATTACH,TAPE19, pfn_4 .	pfn_4 is the file name of
ATTACH,EXEPLT.	the plot instructions
EXEPLT(OUTPUT,TAPE19)	

The output from this routine consists of four items. First, the input file mnemonics are printed, so the user can identify which plots are forthcoming. Then, for each transfer function, three items are printed. The transfer function dipoles (first and second order) which have been cancelled are first, followed by the numerator and denominator of the transfer function. Then, the Bode plot is "drawn." Finally, if a listing was requested in the CHOICES file, it follows the Bode plot. An annotated example is given in Figures 11a, b, and c.

D. INTERFACE WITH PIVIB

Ten of the possible BIODYN-80 transfer functions can be used as input to PIVIB. These are listed in Figure 12. The input file structure for PIVIB is quite lengthy and complex, involving over 200 parameters. An explanation of it is beyond the scope of this user's manual, and the interested reader is referred to Reference 7, the PIVIB User's Manual. A brief outline of the steps used to generate the PIVIB input file is given below.

Each transfer function is to be interpreted as

$$\text{Transfer Function} \equiv \frac{N_{\text{input}}}{\Delta}(s) = \frac{\kappa \left\{ \pi \left(s + \frac{1}{T_z} \right) \right\} \cdot \left\{ \pi \left(s^2 + 2\zeta_z \omega_z s + \omega_z^2 \right) \right\}}{\left\{ \pi \left(s + \frac{1}{T_p} \right) \right\} \cdot \left\{ \pi \left(s^2 + 2\zeta_p \omega_p s + \omega_p^2 \right) \right\}}$$

where π denotes a product of first- or second-order roots, and κ is the so-called "root locus gain" (of the high-frequency asymptote):

$$\kappa = \frac{\text{High Frequency Gain of Numerator}}{\text{High Frequency Gain of Denominator}}$$

and the various first- and second-order poles and zeros are indicated below. The transfer function can also be interpreted in Bode format, as:

$$\text{Transfer Function} \equiv \frac{\kappa \left\{ \pi (T_z s + 1) \right\} \cdot \left\{ \pi \left(\frac{s^2}{\omega_z^2} + \frac{2\zeta_z s}{\omega_z} + 1 \right) \right\}}{\left\{ \pi (T_p s + 1) \right\} \cdot \left\{ \pi \left(\frac{s^2}{\omega_p^2} + \frac{2\zeta_p s}{\omega_p} + 1 \right) \right\}}$$

where K_{OL} is the gain of the low-frequency asymptote ("Bode gain"):

$$K_{OL} = \frac{\text{Low Frequency Gain of Numerator}}{\text{Low Frequency Gain of Denominator}}$$




Figure 9 Format for BIODYN-80 Transfer Function Printouts

Format	Comment
Case title (15A4)	
D\$\$	(Specifies denominator)
NP1, NP2, K _p , 0., 0., 0., 0., 0.	(2I4, G14.6, 5F7.1)
1/T _{p1}	
1/T _{p2}	First-order poles (5X, G14.6)
.	
.	
.	
ζ _{p1} , ω _{p1}	Second-order poles (ζ ₁ , ω ₁)
ζ _{p2} , ω _{p2}	(5X, 2F14.6)
.	
.	
.	
XXX/XXX	First transfer function numerator
NZ1, NZ2, K _z , W1, WF, XU, XL, XP	(2I4, G14.6, 5F7.1)
1/T _{z1}	
1/T _{z2}	First-order zeros (5X, G14.6)
.	
.	
.	
ζ _{z1} , ω _{z1}	
ζ _{z2} , ω _{z2}	Second-order zeros (ζ ₂ , ω ₂)
.	(5X, 2G14.6)
.	
.	
XXX/XXX	Second transfer function numerator
	.
	.
	.

where

NP1 = No. first-order poles	K _z = High-frequency numerator gain
NP2 = No. second-order poles	W1 = Bode plot lower frequency limit
K _p = High-frequency denominator gain	WF = Bode plot upper frequency limit
NZ1 = No. first-order zeros	XU = Bode plot upper phase limit
NZ2 = No. second-order zeros	XL = Bode plot lower phase limit
	XP = Listing switch

Figure 10. Format Used for BIODYN-80 TAPE19 File of Transfer Functions

BIODYN T.F. 05/20/80 15.13.57.
SEATED CREWMAN - VIEWING DISTANCE = 9 CM

Title

D**
RHD/DZF

Dump of file

BIODYN T.F.

BIODYN T.F. 05/20/80 15.13.57.
SEATED CREWMAN - VIEWING DISTANCE = 9 CM

Title

RHD/DZF
D**

FIRST-ORDER DIPOLES CANCELLED :
46.384000
100.00000

SECOND-ORDER DIPOLES CANCELLED :
.44230900 , 8.3929300
.60022000 , 50.002500
.65024400 , 316.83100

NUMERATOR:

-.81361

(0.) (0.) (10.955) (11.950) } First-order zeros
(22.500) (107.75) (535.79)
((.22639 , 8.4561 , 1.9144 , 8.2365))
((.78552 , 13.624 , 10.702 , 8.4311)) } Second-order zeros
((.82761 , 20.272 , 16.777 , 11.379))
((-.16669 , 21.651 , -3.6090 , 21.348))
((.22759 , 47.017 , 10.700 , 45.783))

DENOMINATOR:

(10.957) (11.983) (22.499) (107.81) } First-order poles
(531.02)
((.22869 , 8.4682 , 1.9366 , 8.2437))
((.40550 , 13.701 , 5.5558 , 12.524)) } Second-order poles
((.24026 , 16.682 , 4.0081 , 16.193))
((.82362 , 20.305 , 16.723 , 11.516))
((.94299E-01 , 31.293 , 2.9509 , 31.153))
((.19289 , 46.973 , 9.0608 , 46.091))

-.13857E-02


BIODYN T.F.

BIODYN T.F. 05/20/80 15.13.57.
SEALED CREWMAN - VIEWING DISTANCE = 9 CM

Title

Top scale

XXX is
magnitude



b) Printer-Generated Frequency Response (Bode Plot)

Figure 11 (Continued)

SIIDYN T.F.

SIIDYN T.F.

05/20/80

15.15.37

Title

SEATED CRUISEMAN - VIEWING DISTANCE - 9 CM

RMS/HPZP

364

FREQ	DB	PHS
1.00	-17.11	360.0
1.12	-18.07	360.0
1.26	-18.97	360.0
1.41	-19.91	360.0
1.58	-20.91	360.0
1.78	-21.97	360.0
2.00	-23.00	360.0
2.24	-24.00	360.0
2.51	-25.00	360.0
2.80	-26.00	360.0
3.12	-27.00	360.0
3.48	-28.00	360.0
3.88	-29.00	360.0
4.32	-30.00	360.0
4.80	-31.00	360.0
5.32	-32.00	360.0
5.88	-33.00	360.0
6.48	-34.00	360.0
7.12	-35.00	360.0
7.80	-36.00	360.0
8.52	-37.00	360.0
9.28	-38.00	360.0
10.08	-39.00	360.0
10.92	-40.00	360.0
11.80	-41.00	360.0
12.72	-42.00	360.0
13.68	-43.00	360.0
14.68	-44.00	360.0
15.72	-45.00	360.0
16.80	-46.00	360.0
17.92	-47.00	360.0
19.08	-48.00	360.0
20.28	-49.00	360.0
21.52	-50.00	360.0
22.80	-51.00	360.0
24.12	-52.00	360.0
25.48	-53.00	360.0
26.88	-54.00	360.0
28.32	-55.00	360.0
29.80	-56.00	360.0
31.32	-57.00	360.0
32.88	-58.00	360.0
34.48	-59.00	360.0
36.12	-60.00	360.0
37.80	-61.00	360.0
39.52	-62.00	360.0
41.28	-63.00	360.0
43.08	-64.00	360.0
44.92	-65.00	360.0
46.80	-66.00	360.0
48.72	-67.00	360.0
50.68	-68.00	360.0
52.68	-69.00	360.0
54.72	-70.00	360.0
56.80	-71.00	360.0
58.92	-72.00	360.0
61.08	-73.00	360.0
63.28	-74.00	360.0
65.52	-75.00	360.0
67.80	-76.00	360.0
70.12	-77.00	360.0
72.48	-78.00	360.0
74.88	-79.00	360.0
77.32	-80.00	360.0
79.80	-81.00	360.0
82.32	-82.00	360.0
84.88	-83.00	360.0
87.48	-84.00	360.0
90.12	-85.00	360.0
92.80	-86.00	360.0
95.52	-87.00	360.0
98.28	-88.00	360.0
101.08	-89.00	360.0
103.92	-90.00	360.0
106.80	-91.00	360.0
109.72	-92.00	360.0
112.68	-93.00	360.0
115.68	-94.00	360.0
118.72	-95.00	360.0
121.80	-96.00	360.0
124.92	-97.00	360.0
128.08	-98.00	360.0
131.28	-99.00	360.0
134.52	-100.00	360.0

Listing of frequency
(rad/sec), amplitude (dB)
and phase (deg) at 20
evenly-spaced increments/
decade. (This listing is
only generated if XL = 1.0
in the CHOICES file for this
transfer function)

c) Listing of Frequency Response Values

Figure 11 (Concluded)

Note: \emptyset denotes a typed blank space.

<u>Output</u>	<u>BIODYN TF</u>		<u>PIVIB TF</u>	
Shoulder: (S)	$\frac{\emptyset XS}{BXP}$	-	$\frac{Ch1}{Ch1}_S$	- $\frac{\text{Inertial horizontal shoulder deflection}}{\text{Horizontal platform deflection}}$
	$\frac{\emptyset XS}{BZP}$	-	$\frac{Ch1}{Ch2}_S$	- $\frac{\text{Inertial horizontal shoulder deflection}}{\text{Vertical platform deflection}}$
	$\frac{\emptyset Z1}{BXP}$	-	$\frac{Ch3}{Ch1}_S$	- $\frac{\text{Inertial vertical shoulder deflection}}{\text{Horizontal platform deflection}}$
	$\frac{\emptyset Z1}{BZP}$	-	$\frac{Ch3}{CH2}_S$	- $\frac{\text{Inertial vertical shoulder deflection}}{\text{Vertical platform deflection}}$
Head: (H)	$\frac{DTH}{BXP}$	-	$\frac{Ch3}{Ch1}_H$	- $\frac{\text{Inertial head pitch}}{\text{Horizontal platform deflection}}$
	$\frac{DTH}{BZP}$	-	$\frac{Ch3}{Ch2}_H$	- $\frac{\text{Inertial head pitch}}{\text{Vertical platform deflection}}$
	$\frac{DZH}{BXP}$	-	$\frac{Ch2}{Ch1}_H$	- $\frac{\text{Inertial vertical head deflection}}{\text{Horizontal platform deflection}}$
	$\frac{DZH}{BZP}$	-	$\frac{Ch2}{Ch2}_H$	- $\frac{\text{Inertial vertical head deflection}}{\text{Vertical platform deflection}}$
Stick (C)	$\frac{\emptyset C\emptyset}{DXP}$	-	$\frac{Ch1}{Ch1}_C$	- $\frac{\text{Longitudinal stick deflection}}{\text{Horizontal platform deflection}}$
	$\frac{\emptyset C\emptyset}{DZP}$	-	$\frac{Ch1}{Ch2}_C$	- $\frac{\text{Longitudinal stick deflection}}{\text{Vertical platform deflection}}$

Assumptions: Of the 3 vibration inputs possible, 2 are X and Z. Assume X is Channel 1, Z is Channel 2 for the above table.

Figure 12 BIODYN-80 Transfer Functions Which May Be Used as PIVIB Input

1. Specify title for run
2. BDMOD - enter the biodynamic response module
 - a. FREQS - specify all frequencies required for biodynamic analysis
 - b. VIBR - specify vibration input/source transfer functions
 - c. BIOTR - specify biodynamic transfer functions. This is the interface between BIODYN-80 and PIVIB.
 - d. BDOUT - specify biodynamic outputs for printing
 - e. BCOMP - given all information specified above, compute and print biodynamic quantities
3. PVMOD - enter the pilot/vehicle module
 - a. Specify various P/V parameters in state vector form
 - b. VBINT - controls communication between BDMOD and PVMOD
 - c. PCOMP - perform pilot/vehicle computations and print results
 - d. FDREP - compute and print frequency domain measures, e.g., describing functions, remnants, signal spectra
4. Repeat 2 and 3 for each case
5. END

E. FOR ASSISTANCE

New and inexperienced users should have an experienced INTERCOM or batch user assist them through the first application. For technical questions concerning this program or models, please call or write: Henry R. Jex at Systems Technology, Inc., 13766 S. Hawthorne Blvd., Hawthorne, CA 90250. Telephone Number (213) 679-2281.

APPENDIX A
DEFINITION OF PARAMETERS, SYMBOLS, RANGES AND TYPICAL VALUES

TABLE 1 PARAMETER AND SYMBOL DEFINITIONS, RANGES, AND TYPICAL VALUES

PARAMETER	FORTRAN NAME	UNITS	LOCATION DEFINITION	SOURCE* (Refs.)	REASONABLE RANGE		TYPICAL VALUES (STD CASES)	
					MINIMUM	MAXIMUM	STDPLT†	STDTCRW
LOWER BODY								
M _B	XMB	kg	Lower body mass (Hips)	T(1,2,3)	10.	25.	14.	14.
B _B	BB	n/m/s	Lower body/seat cushion damper	F(1,4,5)	100.	2,000.	1290.1	315.
K _B	XKB	N/m	Lower body/seat cushion stiffness	F(1,4,5)	20,000.	100,000.	29585.	49360.
K _{GS}	GK1	N/m	Series spring gradient in lower body	F(1,4,5)	50,000.	200,000.	71519.	119322.
θ _L	THL	deg	Seat (hips) tilt angle	M(1)	-20.	+80.	13.	13.
G	G	m/s ²	Trim vertical acceleration		0.1	100.	9.8	9.8
TORSO								
M _T	XMT	kg	Torso mass	T(1,2,3)	10.	30.	18.	18.
I _T	ZIT	kg.m ²	Torso inertia	T(1,2,3)	0.5	2.	0.8	0.8
B _{TB}	BTB	$\frac{N.m}{rad/s}$	Torso damping	F(1,4)	10.	100.	16.75	40.
K _{TB}	XKTB	$\frac{N.m}{rad}$	Torso stiffness	G,F(1,4)	100.	2,000.	500.	500.
θ _T	THT	deg	Angle of XLT from vertical	M(1,3,4)	-30.	+90.	10.	-15.
L _T	XLT	m	Torso c.g. to hips pivot length	T,M(1,2,3)	0.12	0.40	0.15	0.15
θ _{TN}	THTN	deg	Angle of XLTN	M,T(1,2,3)	-30.	+90.	5.	-5.
L _{TN}	XLTN	m	Torso c.g. to neck/pivot	T,M(1,2,3)	0.15	0.30	0.3	0.3
θ _S	THS	deg	Angle of XLS	M,T(1,3)	-30.	+90.	5.	-5.
L _S	XLS	m	Torso c.g. to shoulder length		0.10	0.30	0.3	0.3

†"STDPLT" = STD pilot, stiff centerstick

†"STDTCRW" = STD crewman, hand on knees

*Sources Legend: Measured (e.g., photo) or specified by situation
Tabulated, cadaver or anthropometric tables
Fitted, to transfer function data
Guesstimate (on basis of physical properties)

(continued)

TABLE 1. (Continued)

PARAMETER	FORTRAN NAME	UNITS	LOCATION DEFINITION	SOURCE* (Refs.)	REASONABLE RANGE		TYPICAL VALUES (STD CASES)	
					MINIMUM	MAXIMUM,	STDPLT	STDCRW
<u>NECK</u>								
M _N	XMN	kg	Neck mass	T(1,3,6)	0.	3.0	0.0**	1.24
I _N	ZIN	kg.m ²	Neck inertia	T(1,2,3,6)	0.	0.010	0.0**	0.0024
B _N	BNT	N.m rad/s	Neck/torso damper	G,F(1,5)	0.	0.40	0.25	0.1
K _{NT}	XXNT	N.m rad	Neck/torso stiffness	G(1,5)	10.	80.	50.0	50.0
θ _N	THN	deg	Angle of XLN	M(1,3)	-90.	+90.	-20.	-30.
L _N	XLN	m	Neck length	M,T(1,2,3,6)	0.05	0.25	0.1	.12444
L _{NL}	XLNL	m	Neck c.g to neck/ torso pivot	T,G(1,3)	0.02	0.15	0.05	.06222
<u>HEAD/DISPLAY VIEWING</u>								
M _H	XMH	kg	Head mass	T,G(1,2,3,5)	2.0	10.0	4.34	3.1
I _H	ZIH	kg.m ²	Head inertia	T,G(1,2,3,6)	0.010	helmeted 0.100	0.039	0.0303
B _{HN}	BHN	N.m rad/s	Head/neck damper	G,F(1,8)	0.	helmeted 0.40	0.0**	0.126
K _{HN}	XXHN	N.m rad	Head/neck stiffness	G,F(1,4,8)	10.	30.	10.**	15.
G _H	CH	-	Head/neck compliance parameter (CH = 0. locks head on neck)	M(1,8)	0.0 locked	1. unlocked	0.0**	1.
θ _H	TH	deg	Angle of XLG(pivot-CG)	M,T(1,2,3,6)	-30.	+150.	70.	60.
L _T	XLH	m	Head c.g. to head/ neck pivot length	T,M(1,2,3,6)	0.0	0.100	0.0*	0.025
θ _V	THV	deg	Angle of line of sight	M,T(1,3)	-90.	+90.	-30.	-30.
V _D	VD	m	Viewing distance from head/neck pivot	M(1)	0.	1000.	0.75	0.6853

*Sources Legend:

Measured (e.g., photo) or specified by situation

Tabulated, cadaver or anthropometric tables

Fitted, to transfer function data

Guesstimate (on basis of physical properties)

**Head/Neck Locked

TABLE 1. (Continued)

PARAMETER	FORTRAN NAME	UNITS	LOCATION DEFINITION	SOURCE* (Refs.)	REASONABLE RANGE		TYPICAL VALUES (STD CASES)	
					MINIMUM	MAXIMUM	STDPLY	STDGRW
<u>ARMS (Upper, Lower)</u>								
M ₁	XM1	kg	Upper arm mass	T,M(1,2,3)	1.0	4.0	1.372	1.372
I ₁	Z1	kg.m ²	Upper arm inertia	T(1,2,3)	0.01	0.05	0.012	0.012
θ ₁	TI	deg	Upper arm angle	M,T(1,3,8)	-30.0	+90.0	40.	15.
L ₁	D1	m	Upper arm length (= L _a + L _b)	M,T(1,3,8)	0.2	0.5	0.29	0.29
L _a /L ₁	R1	m/m	Upper arm c.g. (fractional distance)	T,G(1,2,3)	0.2	0.6	0.44	0.44
<u>LOWER ARM</u>								
M ₂	XM2	kg	Lower arm mass	T,M(1,2,3)	0.5	3.0	1.017	1.017
I ₂	Z2	kg.m ²	Lower arm inertia	T,(1,2,3)	0.01	0.10	0.0152	0.0152
θ _E	TE	deg	Elbow angle	M,T(1,3,8)	60.0	170.0	145.	115.
L ₂	D2	m	Lower arm length (= L _e + L _d)	M,T(1,3,8)	0.2	0.5	0.305	0.305
L _d /L ₂	R2	m/m	Lower arm c.g. (fractional distance)	T,G(1,2,3)	0.2	0.6	0.5	0.5
<u>GRIP INTERFACE</u>								
θ _{IJ}	TIJ	deg	Grip interface angle	M,G(3)	-45.0	+45.0	0.0	0.0
B _I /K _I	TIF	s	Grip interface time constant	G,F(1,8)	0.0	0.5	0.01	0.1
C _I	CI	m/N	Grip interface compliance K _I -1	M,G,F(1,8)	0.0 fixed	1000.0 "free"	.0000558	1.0

*Sources Legend: Measured (e.g., photo) or specified by situation
 Tabulated, cadaver or anthropometric tables
 Fitted, to transfer function data
 Estimate (on basis of physical properties)

TABLE 1. (Continued)

PARAMETER	FORTRAN NAME	UNITS	LOCATION DEFINITION	SOURCE* (Refs.)	REASONABLE RANGE		TYPICAL VALUES (STD CASES)	
					MINIMUM	MAXIMUM	STDPLT	STDORW
STICK								
M _S	XMS	kg	Stick/hand mass (referred to grip)	M,F(1,8)	0.0	1.0	1.31	4.0
B _S	BS	N/m/s	Stick damper	M,F(1,8)	0.0	5.0	2.	240.0
K _S	XKS	N/m	Stick gradient	M(1,8)	0.01	20,000.0	1300.	10000.0
Q _{KS}	QKS	-	Stick compliance parameter (QKS=0 means that XKS=∞)	M(1)	0.0 "fixed"	1.0 "fixed"	1.0	1.0
S _X	SX	N/g	Bobweight sensitivity to N _X	F,M,G(1,8)	-5.0	+10.0	0.0	0.0
S _Z	SZ	N/g	Bobweight sensitivity to N _Z	F,M,G(1,8)	-10.0	+10.0	0.0	0.0
STICK ANGLE								
θ _c	THC	deg	Stick angle	M(1)	-20.0	+120.0	90.	90.
L _c	XLC	m	Stick length (pivot to center of grip)	M(1)	0.0	2.0	0.61	0.55
K _{SC}	XKSC	Units m	Stick output scale factor (rescales stick displacement to "specified" units (e.g., deg, cm, etc.))	F,G(1,8)	0.01	20,000.0	1300. (N/m)	0.01
ARM REST								
B _{AR}	BAR	N/m/s	Arm rest damper (normal)	M,G(1)	0.0	1.0	0.0†	0.0†
K _{AR}	XKAR	N/m	Arm rest stiffness (normal)	M,G(1)	0.0	10,000.0	0.0†	0.0†
B _F	BAT	N/m/s	Arm rest damper (tangential)	G,M(1)	0.0	150.0	0.0†	0.0†
K _F	XKAT	N/m	Arm rest stiffness (tangential)	G,M(1)	0.0	10,000.0	0.0†	0.0†
L _{ER}	XLER	m	Elbow to arm rest distance	M(1)	0.0	0.5	0.0†	0.0†
A _{MR}	ARMR	-	Fraction of arm weight on arm rest	G(1)	0.0	1.0	0.0†	0.0†

*Sources Legend: Measured (e.g., photo) or specified by situation
 Tabulated, cadaver or anthropometric tables
 Fitted, to transfer function data
 Guesstimate (on basis of physical properties)

†Armrest disabled.

TABLE 1. (Continued)

PARAMETER	FORTRAN NAME	UNITS	LOCATION DEFINITION	SOURCE* (Refs.)	REASONABLE RANGE		TYPICAL VALUES (STD CASES)	
					MINIMUM	MAXIMUM	STOPLT	STOCHW
<u>NEUROMUSCULAR SYSTEM:</u> <u>Actuation Elements:</u>								
NM	NM	-	Switch for central or force activation dynamics 0 for arm control 1 for head/neck control	M	0.0 arm	1.0 head	0.0	0.0
Si	SI	-	Overall scale factor	F,G(1,8)	0.0	200.0	104.4	50.0
K _{lc}	XKLC	N/N	Neuromuscular actuation gain	F,G(1,8)	0.0	1.0	.02044	.02
T _{oc}	TCC	s	Neuromuscular actuation time constant	F,G(1,8)	0.0	0.2	.0909	.0909
cs	TCS	s	Neuromuscular actuation lag	F,G(1,8)	0.0	0.3	0.089	.089
K _a	XKAA	N/N	Gain of force activation dynamics	F,G(1,8)	0.0	10.0	1.	1.
ζ _a	ZA	-	Damping in force activation dynamics	F,G(1,8)	0.0	1.0	0.8	0.8
ω _a	WA	rad/s	Natural frequency in force activation dynamics	F,G(1,8)	10.0	20.0	16.	16.
T _a	TAA	s	Time delay in force activation dynamics	F,G(1,8)	0.0	0.10	0.0	0.0

*Sources Legend: Measured (e.g., photo) or specified by situation
 Tabulated, cadaver or anthropometric tables
 Fitted, to transfer function data
 Guesstimate (on basis of physical properties)

TABLE 1. (Continued)

PARAMETER	FORTRAN NAME	UNITS	LOCATION DEFINITION	SOURCE* (Refs.)	REASONABLE RANGE		TYPICAL VALUES (STD CASES)	
					MINIMUM	MAXIMUM	STDPLY	STDGRW
			NEUROMUSCULAR SYSTEM: <u>Actuation Elements:</u> continued					
B _M	BM	N/m/s	"Hills law" damper	G,F(1,7,8)	0.0	20.0	1.	1.0
K _M	XKM	N.m	Spring in neuromuscular system	G,F(1,7,8)	0.1	20.0	2.	2.
B _e	BE	N/m/s	Series elastic element damper	F(1,7,8)	0.0	10.0	2.431	2.43
K _e	XKE	N/m	Series elastic element gradient	G,F(1,7,8)	0.1	100.0	40.	40.
B _T	BT	N/m/s	Tendon damper	G,F(1,7,8)	0.0	10.0	0.	0.
K _T	XKT	N/m	Tendon gradient	G,F(1,7,8)	0.1	300.0	80.	80.
K _{sp}	XKSP	N/m	Muscle spindle model gain	G(1,7,8)	1.0	10.0	5.	5.
T _{sp}	TSP	s	Muscle spindle lead time constant	G(1,7,8)	0.02	0.15	1/11.	1/11.
T _{ps}	TPS	s	Muscle spindle lag time constant	G(1,7,8)	0.0	0.1	0.0	0.0
T _{ss}	TSS	s	Muscle spindle high frequency lead time constantly	G(1,7,8)	0.0	0.1	0.0	0.0
K _g	XKG	N/N	Golgi tendon organ model gain	G(1,7,8)	0.1	1.0	0.5	0.5
T _g	TG	s	Golgi tendon organ time constant	G(1,7,8)	0.02	0.1	1/18.	1/18.
T _z	TZ	s	Golgi tendon organ time constant	G(1,7,8)	0.0	0.1	0.0	0.0
T _p	TP	s	Golgi tendon organ lag time constant	G(1,7,8)	0.0	0.1	0.0	0.0

*Sources Legend: Measured (e.g., photo) or specified by situation
 Tabulated, cadaver or anthropometric tables
 Fitted, to transfer function data
 Guesstimate (on basis of physical properties)

TABLE 1. (Concluded)

PARAMETER	FORTRAN NAME	UNITS	LOCATION Definition	SOURCE* (Refs.)	REASONABLE RANGE		TYPICAL VALUES (STANDARD CASES)	
					MINIMUM	MAXIMUM	STDPLT	STDORW
<u>IMAGE FIXATION/VESTIBULO- OCULAR SERVO</u>								
K _{DE}	XKDE	rad rad	Fixation error gain	F (9)	1.0	10.0	7.08	7.08
K _{RE}	XKRE	rad rad/s	Fixation rate gain	F (9)	0.0	10.0	0.0	0.0
τ _v	TV	s	Time delay in fixation loop	F (9)	0.0	0.10	0.045	0.045
α	ALPHA	rad/s	"Pseudo Integrator" break frequency	G, F(9)	0.0	0.5	0.3	0.3
K _p	XKP	rad rad	Target pursuit gain (Optional)	G (9)	0.0	1.0	0.0	0.0
K _{IE}	XKIE		Position gain from "Vestibular" sensor	F (9)	0.1	1.0	0.67	0.67
K _{VE}	XKVE		Velocity gain from "Vestibular" sensor	F (9)	0.0	0.1	0.1	0.1
T _{c2}	TC2		"Vestibular" lag	F, T(9)	0.005	0.015	0.01	0.01
T _{EM}	TEM	s	Ocular Servo Lag time constant	F (9)	0.05	0.10	0.1	0.1
T _{LM}	TLM	s	Ocular Servo Lead time constant	F (9)	0.010	0.020	0.0125	0.0125
Q _E	QE		Switch for fast mode in Ocular Servo 1. use Z _E , W _E 0. W _E = infinity	M	0.0 (ω _E = ∞)	1.0	1.0	1.0
ζ _e	ZE	-	Ocular Servo Damping Ratio	F (9)	0.2	1.0	0.65	0.65
ω _e	WE	rad/s	Ocular Servo Natural frequency	F (9)	200.0	400.0	316.23	316.23

*Sources Legend: Measured (e.g., photo) or specified by situation
 Tabulated, cadaver or anthropometric tables
 Fitted, to transfer function data
 Guesstimate (on basis of physical properties)

TABLE 2. PARAMETER FILE STRUCTURE (SHORT FORMAT)

A. Lower Body

M_B B_B K_B K_{BS} θ_L G

B. Torso

M_T I_T B_{TB} K_{TB}

θ_T L_T θ_{TN} L_{TN} θ_s L_s

C. Neck

M_N I_N B_{NT} K_{NT}

θ_N L_N L_{N1}

D. Head/Display Viewing

M_H I_H B_{HN} K_{HN} C_H

θ_H L_H θ_V V_D

E. Arms (Upper then lower)

M_1 I_1 θ_1 L_1 L_a/L_1

M_2 I_2 θ_E L_2 L_d/L_2

F. Grip Interface

θ_{IJ} B_I/K_I C_I

G. Stick

M_s B_s K_s C_{KS} S_x S_z

θ_c L_c K_{sc}

H. Arm Rest

B_{AR} K_{AR} B_F K_F L_{ER} Arm_R

I. Neuromuscular System

NM S_i

K_{1c} T_{cc} τ_{cs}

K_a ζ_a ω_a τ_a

B_M K_M B_e K_e B_T K_T

K_{sp} T_{sp} T_{ps} T_{ss}

K_g T_g T_z T_p

J. Image Fixation/Vestibulo-Ocular Servo

K_{DE} K_{RE} τ_v α K_p

K_{IE} K_{VE} T_{c2}

T_{EM} T_{LM} Q_E ζ_e ω_e

APPENDIX B
DEFINITION OF FORCING FUNCTION AND
RESPONSE VARIABLES

TABLE 3 INPUT (FORCING FUNCTION) VARIABLES

MATRIX COLUMN NUMBER	INPUT VARIABLE NAME	COLUMN CODE*	UNITS	POSITIVE DIRECTION	DEFINITION AND USAGE
1	N _{zp}	NZP	g	Upward	Platform acceleration
2	Δ_{zp}	DZP	m	Upward	Platform deflection
3	N _{xp}	NXP	g	Forward	Platform acceleration
4	Δ_{xp}	DXP	m	Forward	Platform deflection
5	F _D	\emptyset FD	N	Forward	Force input to stick
6	B _{zp}	BZP	m	Upward	Special Platform deflection+
7	B _{xp}	BXP	m	Forward	Special Platform deflection+
8	NMC	NMC	N		Neuromuscular command within CNS
9	θ_{TI}	TTI	rad		Test input into fixation error

*Small "b" represents a typed-blank space.

+These are used to get transfer functions of $\frac{\text{Inertial shoulder (or head) motion}}{\text{Platform motion}}$

TABLE 4 OUTPUT (RESPONSE) VARIABLES

MATRIX COLUMN NUMBER	RESPONSE VARIABLE NAME	MATRIX COLUMN CODE*	UNITS	POSITION DIRECTION	DEFINITION AND USAGE
1	c	$\beta C \beta$	m or N	Forward	Stick output (K_{CS} used to scale as force)
2	f_{ca}	FCA	N	Forward on stick	Interface force at stick grip
3	Δz_l	βZ_l	m	Upward	Vertical shoulder deflection relative to platform ($z_s - z_p$)
4	$\Delta \theta_l^+$	DTL	rad	Pitch up	Lower arm angle
5	$\Delta \theta_a$	DTA	rad	Pitch up	Lower arm angle
6	f_{ly}	FLY	rad	Up on upper arm	Vertical interface force at elbow
7	F_M	βFM	N		Muscle model force referred to upper arm c.g.
8	L_I	βLI	N	Forward	Grip interface deflection (stick to lower arm)
9	f_{lx}	FLX	N	Forward on upper arm	Horizontal interface force at elbow
10	x_m	βXM	m		Internal state in muscle model
11	f_{rs}	FNS	N	Forward on upper arm	Horizontal interface force at shoulder/upper arm
12	f_{vs}	FVS	N	Up on upper arm	Vertical interface force at shoulder/upper arm
13	x_s	βXS	m	Forward	Horizontal shoulder deflection relative to platform ($x_s - x_p$)
14	$\Delta \theta_T$	DTT	rad	Pitch up	Torso rotation
15	f_{nh}	FNH	N	Forward on	Head/neck interface force
16	$\Delta \theta_H$	DTH	rad	Pitch up	Head rotation
17	f_{vh}	FVH	N	Up on head	Head/neck interface force
18	f_{by}	FBY	N	Up on Torso	Vertical hips/torso interface force
19	F_{bx}	FBX	N	Forward on hips	Hips/torso interface force

*Note: Small "b" represents a typed-blank space.

#Note: $\Delta \theta_l$ (Column 4) means small signal perturbation of θ_l given in fig. 3

TABLE 4 (Continued)

MATRIX COLUMN NUMBER	RESPONSE VARIABLE NAME	MATRIX COLUMN CODE*	UNITS	POSITIVE DIRECTION	DEFINITION AND USAGE
20	u_{sp}	USP	m	Up the seat back	Internal state in hip model
21	u_{bp}	UBP	m	Up the seat back	Hip deflection relative to platform (parallel to seat-back)
22	x_1	βx_1	m		Internal state in muscle model
23	$\Delta \theta_N$	DTN	rad	Pitch up	Neck rotation
24	f_{nN}	FNN	N	Forward on neck	Neck/torso horizontal interface force
25	f_{vN}	FVN	N	Up on neck	Neck/torso vertical interface force
26	RHD	RHD	deg	Up relative to display	Head point of Regard relative to a display on the platform
27	A_a	βA_a	N		Muscle model command out of spinal cord
28	F_A	βF_A	N		Commanded force out of force activation dynamics
29	f_{aa}	FAA	N		Internal state in force activation
30	A_g	βA_g	N		Output of golgi tendon organ sensors
31	A_c	βA_c	N		Spinal cord command
32	A_e	βA_e	N		Error between neuromuscular command and proprioceptive stick force
33	x_{sp}	x_{sp}	m		Muscle length change sensed by spindle model
34	Δr_n	DRN	m		Relative normal deflection of arm and rest
35	Δr_t	DRT	m		Relative tangential deflection of arm and rest
36	Δz_h	DZH	m		Vertical component of head motion relative to platform

*Note: Small "b" represents a typed-blank space.

TABLE 4 (Concluded)

MATRIX COLUMN NUMBER	RESPONSE VARIABLE NAME	MATRIX COLUMN CODE*	UNITS	POSITIVE DIRECTION	DEFINITION AND USAGE
37	A_{c1}	AC1	rad		Output of compensatory action in eye fixation loop
38	A_{E1}	AEI	rad		Output of "Pseudo Integrator"
39	θ_{MC}	TMC	rad		Command to Ocular Servo
40	A_v	bAV	r/s	Head up	Output of "Vestibular" Sensor
41	θ_{EH}	TEH	rad	Up	Eye rotation relative to head
42	θ_{M1}	TM1	rad		Internal node in Ocular Servo
43	θ_I	THI	rad	Up	Fixation error
44	RED	RED	m	Eye up rel. to display	Relative eye point of regard at display
45	θ_{TC}	TTC	rad		Output of "Image Pursuit" operation
46	Z_T	$\emptyset ZT$	m	Up	Display inertial displacement (vertical)
47	θ_E	THE	rad	Up	Inertial eye rotation
48	Δx_h	DXH	m	Forward	Horizontal component of head motion relative to platform

*Note: Small "Ø" represents a typed-blank space.

APPENDIX C
EQUATIONS OF MOTION

$$1 \quad \text{if } C_{K_S} \neq 0$$

$$(\sin \theta_c) c - x_s - L_1(\cos \theta_1) \Delta \theta_1 + L_2(\sin \theta_a) \Delta \theta_a - L_I(\cos \theta_{IJ}) = -B_{x_p}$$

$$2 \quad \begin{array}{cc} \text{if } C_{K_S} \neq 0 & \text{if } C_{K_S} = 0 \\ \hline \left\{ -(M_s s^2 + B_s s + K_s) - \frac{S_x}{L_c} - M_2(\cos \theta_c)^2 s^2 \right\} c / K_{sc} - c \\ + (\sin \theta_c) L_{ca} + (\cos \theta_c) L_{1y} - M_2(\cos \theta_c)(\sin \theta_{IJ}) s^2 L_I \\ - M_2 L_d(\cos \theta_c)(\cos \theta_a) s^2 \Delta \theta_a + (\cos \theta_c)(B_{AR} s + K_{AR})(\Delta x_n) \\ + (\cos \theta_c)(B_{FS} + K_F)(\Delta x_t) \\ = - (z/g + M_2 \cos \theta_c) a_{z_p} - S_x/g a_{x_p} - F_d \end{array}$$

$$3 \quad \text{if } C_{K_S} \neq 0$$

$$\Delta z_1 + L_1(\sin \theta_1) \Delta \theta_1 + L_2(\cos \theta_a) \Delta \theta_a + L_I(\sin \theta_{IJ}) + \frac{(\cos \theta_c)}{K_{sc}} c = 0$$

$$4 \quad \left\{ I_1 s^2 + (L_d M_1 g + L_1 M_2 g - L_1 F_{av0}) \cos \theta_1 \right\} \Delta \theta_1 - L_b(\sin \theta_1) f_{1y}$$

$$+ L_b(\cos \theta_1) f_{1x} + L_a(\cos \theta_1) f_{ns} + L_a(\sin \theta_1) f_{vs} - S_1 L_a F_M = 0$$

NOTE: $F_{av0} = \text{Arm}_R (M_1 + M_2)g$; $\theta_a = 90 + \theta_1 - \theta_E$;

$$a_{z_p} = g N z_p + s^2(\Delta z_p + B z_p) ; a_{x_p} = g N x_p + s^2(\Delta x_p + B x_p)$$

$$\begin{aligned}
5 \quad & \left\{ (I_2 + M_2 L_d^2 \cos^2 \theta_a) s^2 + (F_{av0} - M_2 g) L_e \sin \theta_a \right\} \Delta \theta_a - L_e (\sin \theta_a) f_{1x} \\
& - L_2 (\cos \theta_a) f_{1y} - L_d (\sin \theta_a) f_{ca} \\
& - (L_e - L_{ER} + L_d \cos^2 \theta_a) (B_{AR} s + K_{AR}) \Delta r_n \\
& - (L_d \sin \theta_a \cos \theta_a) (B_F s + K_F) \Delta r_t \\
& + \frac{\text{if } C_{K_s} \neq 0}{K_{sc}} \left\{ L_d M_2 (\cos \theta_a) (\cos \theta_c) s^2 c + L_d (\cos \theta_a) M_2 (\sin \theta_{IJ}) s^2 L_I \right\} = L_d (\cos \theta_a) M_2 a_{zp}
\end{aligned}$$

$$6 \quad f_{1y} + f_{vs} - M_1 s^2 \Delta z_1 - M_1 L_a (\sin \theta_1) s^2 \Delta \theta_1 = M_1 a_{zp}$$

$$\begin{aligned}
8 \quad & C_I (\cos \theta_{IJ}) f_{ca} + \left\{ C_I (\sin \theta_{IJ})^2 M_2 s^2 + B_I / K_I + 1 \right\} L_I \\
& + C_I (\sin \theta_{IJ}) (\cos \theta_a) M_2 L_d s^2 \Delta \theta_a \\
& + \frac{\text{if } C_{K_s} \neq 0}{K_{sc}} \left\{ C_I (\sin \theta_{IJ}) (\cos \theta_c) M_2 s^2 c - C_I (\sin \theta_{IJ}) f_{1y} \right\} \\
& + C_I (\sin \theta_{IJ}) [- (B_F s + K_F) (\sin \theta_a) \Delta r_t] \\
& = C_I (\sin \theta_{IJ}) M_2 a_{zp} \\
& + C_I (\sin \theta_{IJ}) [- (B_{AR} s + K_{AR}) (\cos \theta_a) \Delta r_n]
\end{aligned}$$

$$\begin{aligned}
9 \quad & \frac{\text{if } C_{K_s} \neq 0}{K_{sc}} \left\{ -M_2 (\sin \theta_c) s^2 c + M_2 (\cos \theta_{IJ}) s^2 L_I - \left\{ (M_2 L_d \sin \theta_a) s^2 + F_{av0} \right\} \Delta \theta_a \right. \\
& \left. + f_{1x} - f_{ca} - (B_F s + K_F) (\cos \theta_a) \Delta r_t + (B_{AR} s + K_{AR}) (\sin \theta_a) \Delta r_n \right\} = M_2 a_{xp}
\end{aligned}$$

$$11 \quad f_{ns} - f_{1x} - M_1 s^2 x_s - M_1 L_a (\cos \theta_1) s^2 \Delta \theta_1 = M_1 a_{xp}$$

$$12 \quad f_{vs} + f_{VN} - f_{by} + M_T (\cos \theta_L) s^2 u_{bp} - M_T L_T (\sin \theta_T) s^2 \Delta \theta_T = -M_T a_{zp}$$

$$13 \quad x_s + (\sin \theta_L) u_{bp} + (L_T \cos \theta_T + L_s \cos \theta_s) \Delta \theta_T = B_{xp}$$

$$14 \quad [L_T s^2 + (B_{TB} + B_{NT})s + K_{TB} + K_{NT} - W_E] \Delta \theta_T - (B_{NTS} + K_{NT}) \Delta \theta_N \\ - (L_s \cos \theta_s) f_{ns} - L_{TN} (\cos \theta_{TN}) f_{nN} - L_s (\sin \theta_s) f_{vs} \\ - L_{TN} (\sin \theta_{TN}) f_{VN} + L_T (\cos \theta_T) f_{bx} \\ - L_T (\sin \theta_T) f_{by} + S_1 L_a F_M = 0$$

$$W_E = L_T \cos \theta_T [(M_H + M_N + M_T + M_1 + M_2)g - F_{avO}] \\ + L_s \cos \theta_s [(M_1 + M_2)g - F_{avO}] + L_{TN} \cos \theta_{TN} (M_H + M_N)g$$

$$15 \quad f_{nh} + M_H (\sin \theta_L) s^2 u_{bp} + M_H (L_T \cos \theta_T + L_{TN} \cos \theta_{TN}) s^2 \Delta \theta_T \\ + M_H L_N (\cos \theta_N) s^2 \Delta \theta_N + M_H L_H (\cos \theta_H) s^2 \Delta \theta_H = M_H a_{xp}$$

$$16 \quad [(I_H s^2 + B_{HNS} - M_H g L_H \cos \theta_H) C_H + K_{HN}] \Delta \theta_H + F_A \quad \text{if } NM \neq 0 \\ - (B_{HN} C_H s + K_{HN}) \Delta \theta_N - C_H L_H (\sin \theta_H) f_{vh} - C_H L_H (\cos \theta_H) f_{nh} = 0$$

$$17 \quad f_{vh} - M_H (\cos \theta_L) s^2 u_{bp} + M_H (L_T \sin \theta_T + L_{TN} \sin \theta_{TN}) s^2 \Delta \theta_T \\ + M_H L_N (\sin \theta_N) s^2 \Delta \theta_N + M_H L_H (\sin \theta_H) s^2 \Delta \theta_H = M_H a_{zp}$$

$$18 \quad (\cos\theta_L)f_{by} + (B_Bs + K_B)u_{bp} + (\sin\theta_L)f_{bx} + M_Bs^2u_{bp} = M_B(\sin\theta_L)a_{xp} \\ - M_B(\cos\theta_L)a_{zp}$$

$$19 \quad f_{bx} + f_{nN} + f_{ns} - M_T L_T (\cos\theta_T) s^2 \Delta\theta_T - M_T (\sin\theta_L) s^2 u_{bp} = -M_T a_{xp}$$

$$20 \quad \left(\frac{B_Bs + K_B}{K_{BS}} + 1 \right) u_{bp} - u_{bp} = 0$$

$$21 \quad (\cos\theta_L)u_{bp} - (L_T \sin\theta_T + L_S \sin\theta_S) \Delta\theta_T - \Delta z_1 = 0 - B_{zp}$$

$$23 \quad [I_N s^2 + B_{NT} s + K_{NT} - (M_H g L_N + M_N g L_{N1}) \cos\theta_N] \Delta\theta_N \\ - L_{N1} (\sin\theta_N) f_{VN} - L_{N1} (\cos\theta_N) f_{nN} - [(L_N - L_{N1}) \sin\theta_N + L_H \sin\theta_H] f_{vh} \\ - [L_H \cos\theta_H + (L_N - L_{N1}) \cos\theta_N] f_{nh} + [I_H s^2 - M_H g L_H \cos\theta_H] \Delta\theta_H \\ - (B_{NT} s + K_{NT}) \Delta\theta_T = 0$$

$$24 \quad f_{nN} - f_{nh} + M_N (\sin\theta_L) s^2 u_{bp} + M_N (L_T \cos\theta_T + L_{TN} \cos\theta_{TN}) s^2 \Delta\theta_T \\ + M_N (L_{N1} \cos\theta_N) s^2 \Delta\theta_N = M_N a_{xp}$$

$$25 \quad f_{VN} - f_{vh} - M_N (\cos\theta_L) s^2 u_{bp} + M_N (L_T \sin\theta_T + L_{TN} \sin\theta_{TN}) s^2 \Delta\theta_T \\ + M_N (L_{N1} \sin\theta_N) s^2 \Delta\theta_N = M_N a_{zp}$$

NEUROMUSCULAR MODEL EQUATIONS

$$7 \quad F_M + (B_T s + K_T) L_a(\Delta \theta_1) - (B_T s + K_T) x_m = 0$$

$$10 \quad F_M + (B_e s + K_e) x_m - (B_e s + K_e) x_1 = 0$$

$$22 \quad F_M - (B_M s + K_M) L_a(\Delta \theta_T) + (B_M s + K_M) x_1 + \underbrace{F_A}_{\text{if NM} = 0} = 0$$

$$27 \quad (T_{pss} + 1)(A_a + A_g - A_c) - \underbrace{K_{sp}(T_{sp} s + 1)(T_{ss} s + 1)}_{\text{if NM} = 0} x_{sp} = 0$$

$$28 \quad (\tau_a s + 2) F_A + K_a (\tau_a s - 2) F_{aa} = 0$$

$$29 \quad \underbrace{\left[1 + \frac{2\zeta_a}{\omega_a} s + \frac{s^2}{\omega_a^2} \right]}_{\substack{\text{This set to 1.0} \\ \text{if } \omega_a = 0}} F_{aa} - F_{aa} = 0$$

$$30 \quad (T_p s + 1) A_g + \underbrace{K_g(T_g s + 1)(T_z s + 1)}_{\text{if NM} = 0} F_M = 0$$

$$31 \quad (\tau_{cs} s + 2)(T_{cc} s + 1) A_c + K_{1c}(\tau_{cs} s - 2) A_E = 0$$

32

$$NM = 0$$

$$\begin{aligned} & \left(\frac{M_c}{K_{sc}} \cos^2 \theta_c s^2 \right) c - \sin \theta_c f_{ca} + (M_2 L_d \cos \theta_a \cos \theta_c s^2) \Delta \theta_a - \cos \theta_c f_{ly} \\ & + (M_2 \sin \theta_{IJ} \cos \theta_c s^2) L_I - (B_{AR} \cos \theta_a \cos \theta_c s + K_{AR} \cos \theta_a \cos \theta_c) \Delta r_n \\ & - (B_F \sin \theta_a \cos \theta_c s + K_F \sin \theta_a \cos \theta_c) \Delta r_t + A_E \\ & = M_2 \cos \theta_c a_{zp} + NMC \end{aligned}$$

$$NM = 1$$

$$A_E + RHD/VD = NMC$$

33

$$x_{sp} + L_a \Delta \theta_T - x_m = 0$$

26

$$\begin{aligned} & [L_T \sin(\theta_T - \theta_V) + L_{TN} \sin(\theta_{TN} - \theta_V)] \Delta \theta_T - V_D \Delta \theta_H - \cos(\theta_L - \theta_V) u_{bp} \\ & + L_N \sin(\theta_N - \theta_V) \Delta \theta_N + RHD = B_{zp} \cos \theta_V - B_{xp} \sin \theta_V \end{aligned}$$

34

$$\Delta r_n + \frac{\overbrace{c \cos(\theta_c - \theta_a)}^{\text{if } C_{K_S} \neq 0}}{K_{sc}} + (L_2 - L_{ER}) \Delta \theta_a + L_I \sin(\theta_a - \theta_{IJ}) = 0$$

35

$$\Delta r_t - c \frac{\overbrace{\sin(\theta_c - \theta_a)}^{\text{if } C_{K_S} \neq 0}}{K_{sc}} + L_I \cos(\theta_a - \theta_{IJ}) = 0$$

$$36 \quad \Delta z_H + (L_T \sin \theta_T + L_{TN} \sin \theta_{TN}) \Delta \theta_T$$

$$- (\cos \theta_L) u_{bp} + (L_N \sin \theta_N) \Delta \theta_N = B_{Z_P}$$

$$37 \quad (2 + \tau_V s) A_{C1} + (\tau_V s - 2)(K_{RE} s + K_{DE}) \theta_I = 0$$

$$38 \quad (s + \alpha) A_{EI} + A_{C1} + K_{IE} A_V = 0$$

$$39 \quad \theta_{MC} - \theta_{TC} - A_{EI} + K_{VE} A_V = 0$$

$$40 \quad (T_{C2} s + 1) A_V - s \Delta \theta_H = 0$$

$$41 \quad Q_E = 0 \quad \{ \theta_{EH} - \theta_{M1} = 0$$

$$Q_E = 1 \quad \left\{ \left(1 + \frac{2\zeta_e}{\omega_e} s + \frac{s^2}{\omega_e^2} \right) \theta_{EH} - \theta_{M1} = 0 \right.$$

$$42 \quad (1 + T_{EM} s) \theta_{M1} - (1 + T_{LM} s) \theta_{MC} = 0$$

$$43 \quad \theta_I - \frac{RED}{V_D} = \theta_{TI}$$

$$44 \quad [L_T \sin(\theta_T - \theta_V) + L_{TN} \sin(\theta_{TN} - \theta_V)] \Delta \theta_T - V_D \Delta \theta_H$$

$$- u_{bp} \cos(\theta_L - \theta_V) + \Delta \theta_N L_N \sin(\theta_N - \theta_V) - V_D \theta_{EH} + RED$$

$$= B_{Z_P} \cos \theta_V - B_{X_P} \sin \theta_V$$

$$45 \quad \theta_{TC} - \frac{K_p}{V_D} z_D = 0$$

$$46 \quad z_D = \Delta z_p$$

$$47 \quad \theta_E - \Delta\theta_H - \theta_{EH} = 0$$

$$48 \quad \Delta x_h + (\sin\theta_L)u_{bp} + (L_T \cos\theta_T + L_{TN} \cos\theta_{TN})\Delta\theta_T + L_N(\cos\theta_N)\Delta\theta_N = B_{x_p}$$

APPENDIX D

TYMSHARE EXAMPLE PROBLEM

This appendix documents the use of CREATE, BIODYN and PLOT on the Tymshare System 31 PDP 10.* The computer dialog appears on the next several pages for a typical session. An existing PARAMETER file is modified, a CHOICES file is created, BIODYN generates the requested transfer functions (only one of which is illustrated), and PLOT produces a quick-look Bode plot. Throughout the dialog, all user inputs/ responses are underlined. The following 6 character filenames are accessed in the course of this example (these are not the Standard Pilot and Standard Crewman which are available on Tymshare):

	<u>File Name</u>	<u>Title</u>
Existing PARAMETER file:	BB19	"Stiff Stick"
Modified PARAMETER file:	SEMI	"Semi-Supine"
CHOICES file:	CHOSAR	
TF file:	TAPE19	

There are several differences between the CDC version of the BIODYN-80 package and its Tymshare counterpart. These are listed below:

- All three programs run interactively on Tymshare; all files are specified by the user during execution.
- CHOICES filename can be an existing file, whose name is to be modified. (In CDC, the CHOICES filename must be a new name.)

*A user planning to use BIODYN-80 on Tymshare should be familiar with the Tymshare manual, XEXEC, especially Section 3. At present, BIODYN-80 is not a current Tymshare Library Program, and a potential user should contact the second author for the required procedures.

- Because of the above differences, there are slight changes in the dialog for the Tymshare version (e.g., the NEW PARAMETER FILE? query is not used, since the PDP-10 software can determine internally whether or not a new filename has been input).

D.1 Running CREATE

EXEC CREATE

LOADING
EXECUTION

Execute CREATE

INPUT PARAMETER FILENAME :

PR19

LISTING DESIRED?

IF

(LONG OR (SHORT) LISTING?

SH

PARAMETERS FOR:

STIFF STICK

LOWER BODY

11.000 1290.1 29585. 71519. 13.000 9.8000

TORSO

18.000 0.80000 15.750 500.00 0.00000 0.30000

10.000 0.15000 5.0000 0.30000 0.00000 0.30000

NECK

0.00000 0.00000 0.25000 50.000 0.00000 0.00000

-20.000 0.10000 0.50000E 01

HEAD DISPLAY VIEWING

4.3400 0.39000E-01 0.00000 1.0000 0.00000

70.000 0.00000 -20.000 0.75000

ARM (UPPER, LOWER)

1.3720 0.12000E-01 40.000 0.29000 0.11000

1.0170 0.15000E-01 145.00 0.30500 0.50000

GRIFF INTERFACE

0.0000 0.10000E-01 0.55781E-04

STICK

0.31000 2.0000 13900. 1.0000 0.00000 0.00000

90.000 0.81000 13900.

ARM REST

0.00000 0.00000 0.00000 0.00000 0.00000 0.00000

NEUROMUSCULAR SYSTEM

0 01.40

0.00417E-01 0.90709E-01 0.89888E-01

1.0000 0.00000 16.000 0.00000

1.0000 0.0000 2.4312 40.000 0.00000 80.000

5.0000 0.10900E-01 0.00000 0.00000

0.50000 0.55556E-01 0.00000 0.00000

IMAGE FIXATION/VESTIBULO-OCCULAR SERV

7.0775 0.00000 0.10000E-01 0.30000 0.00000

0.67000 0.10000 0.10000E 01

0.10000 0.10000E-01 1.0000 0.65000 416.23

CHANGES DESIRED?

YE

INPUT NUMERICAL CHANGES AND VALUE FOR EACH CHANGE,
TO EXIT, TYPE XXX.

THE 1.000

TH 110.

XXX

Interactive input of
PARAMETER file to be
modified

Generate short listing
of file to modify

Make changes to file

(continued on next page)

[illegible]

Interactive input
of filename on which
to store modified
PARAMETER file

60

D.1 (Concluded)

INPUT CHOICES FILENAME :	}		Interactive input of CHOICES filename
<u>CHOSAR</u>			
BIODYN IFS DESIRED FOR PIVIB ?	}		No PIVIB TF's desired
<u>NO</u>			
TRANSFER FUNCTION INPUT :		}	Format for CHOICES file information input
FIRST LINE-RESPONSE MNEMONIC, FORCING FUNCTION MNEMONIC (AAA,AAA) ; ENTER XXX TO STOP			
SECOND LINE-PLOTTING INFORMATION, 5 ITEMS :			
BODE LOWER FREQ. LIMIT			
BODE UPPER FREQ. LIMIT			
BODE UPPER PHASE LIMIT (0. DEFAULTS TO 200.)			
BODE LOWER PHASE LIMIT (0. DEFAULTS TO -400.)			
LIST (1. TO LIST TABLE, 0. FOR NO LIST)			
IF NO PLOT DESIRED, ENTER 0. FOR ALL ITEMS			
<u>C,NZP</u>	}		Input CHOICES file information
<u>1.,100.,0.,0.,0.</u>			
<u>21,BZF</u>			
<u>1.,100.,0.,0.,0.</u>			
<u>PTH,BZF</u>			
<u>1.,100.,0.,0.,1.</u>			
<u>XXX</u>			
EXIT	←		Exit CREATE

D.2 Running BIODYN

EXEC BDNBO,NIRFN
LOADING
EXECUTION

Execute BIODYN

ENTER INPUT FILE NAME: SEMI
ENTER CHOICES FILE NAME: CHOSAR

Interactive input of
PARAMETER and CHOICES
files

11-Mar-80 11:53

BIODYN execution

CASE: SEMI-SUPINE

Case title

ENTER SYSTEM OUTPUTS FILE NAME: TAPE20
NEW FILE

Interactive input of
TF file

FLOATING UNDERFLOW FC=111246
FLOATING UNDERFLOW FC=111246

DENOMINATOR:

```
.10444E-26
( 16.591 ) ( 46.384 ) ( 56.079 ) ( 97.512
( 100.00 ) ( 285.86 ) ( 353.22 )
( 1.44231 , 8.3929 , 3.7123 , 7.5273 )
( 1.25697 , 11.509 , 2.9060 , 10.929 )
( 1.20726 , 13.642 , 2.8274 , 13.346 )
( 1.19865 , 24.860 , 4.9386 , 24.365 )
( 1.32015 , 32.898 , 10.532 , 31.167 )
( 1.85789 , 32.931 , 28.251 , 16.921 )
( 1.19448 , 57.685 , 11.219 , 56.583 )
( 1.65024 , 316.83 , 206.02 , 240.70 )
.18027E+11
```

Printout of DTH/DZP
transfer function

NUMERATOR: DTH/DZP

```
.29296E-27 << .28049 >>
( 1.00000 ) ( 1.00000 ) ( -10.621 ) ( 16.590 )
( 46.384 ) ( 97.067 ) ( 100.00 ) ( -138.57 )
( 209.05 )
( 1.44231 , 8.3929 , 3.7123 , 7.5273 )
( 1.21687 , 11.488 , 2.4913 , 11.214 )
( 1.98984 , 16.317 , 16.646 , 2.3916 )
( 1.95130 , 33.163 , 28.232 , 17.400 )
( 1.70646 , 55.410 , 11.440 , 54.216 )
( 1.65024 , 316.83 , 206.02 , 240.70 )
( 1.26657 , 336.66 , 325.41 , 86.321 )
.67996E+08 .37719E+02
```

(See Figure 9 for
explanation of
format)

TRU =123.31 11-Mar-80 11:58

EXIT

Exit BIODYN

D.3 Running PLOT

EXEC GCPLOT,CCUR,CRODTP
LOADING
EXECUTION

ENTER TRFN SYSTEM FILE NAME: TAPE20

M.TMP 11-Mar-80 11:53
SCMT-SUPINE

\$\$\$
C /NZP
Z1/DZF
DTH/DZF

Execute PLOT

Interactive entry
of TF file

Case title

Dump of TF file
contents

TAPE20

M.TMP 11-Mar-80 11:53
SCMT-SUPINE

DTH/DZF
\$\$\$

FIRST ORDER DIPOLES CANCELLED :
16.381000
100.000000

SECOND-ORDER DIPOLES CANCELLED :
11.110000 , 8.3929400
1.5024400 , 316.83100

NUMERATOR:

1.28049				
(1.00000)	(1.00000)	(-10.621)	(16.590)	
(97.057)	(-138.57)	(109.05)		
(1.21687)	(11.488)	(2.4215)	(11.214))
(1.93984)	(14.817)	(16.646)	(24.3917))
(1.85130)	(33.163)	(28.230)	(17.400))
(1.29646)	(55.410)	(11.140)	(54.216))
(1.96807)	(335.66)	(325.41)	(84.321))

DENOMINATOR:

(14.091)	(55.079)	(97.512)	(285.86)	
(353.1)				
(1.20427)	(11.309)	(2.9060)	(10.929))
(1.10026)	(13.642)	(2.8274)	(13.346))
(1.12865)	(21.860)	(4.9586)	(24.365))
(1.32915)	(12.398)	(10.532)	(31.167))
(1.85289)	(52.931)	(28.251)	(16.921))
(1.12448)	(57.685)	(11.219)	(56.583))

PLOT execution


Transfer function DTH/DZF

Identical roots in numera-
tor and denominator are
cancelled; close pairs are
retained

Transfer function to
be plotted (see
Figure 11 for explana-
tion of format)

(Continued on next page)

D.3 (Continued)



(Continued on next page)

D.3 (Concluded)

TAPE TO
M. THE 11-MAR-80 11:53
SERIAL-SUPINE

R/S	DB	DTH/DZF DEG
1.00	-48.34	175.9
1.12	-46.31	175.4
1.26	-44.27	174.9
1.41	-42.21	174.3
1.58	-40.15	173.5
1.78	-38.07	172.8
2.00	-35.96	171.9
2.24	-33.83	170.8
2.51	-31.67	169.7
2.82	-29.46	168.4
3.16	-27.20	167.0
3.55	-24.88	165.3
3.98	-22.48	163.4
4.47	-19.97	161.2
5.01	-17.34	158.6
5.62	-14.56	155.5
6.31	-11.58	151.7
7.08	-8.38	147.1
7.94	-4.91	141.1
8.91	-1.17	133.2
10.00	2.85	122.9
11.22	7.30	110.0
12.59	12.34	89.2
14.13	16.45	56.6
15.85	18.74	24.4
17.78	20.72	-1.7
19.95	23.31	-27.3
22.39	26.34	-60.1
25.12	28.34	-104.6
28.18	27.92	-150.8
31.62	26.04	-189.7
35.48	23.40	-221.9
39.81	20.29	-246.8
44.67	17.12	-264.3
50.12	14.43	-275.8
56.23	12.60	-285.8
63.10	10.82	-299.4
70.79	9.59	-311.4
79.43	8.37	-320.3
89.13	7.35	-327.3
100.00	6.61	-333.2

EXIT

4

Listing of frequency (rad/sec),
amplitude (dB) and phase (deg)
at 20 evenly-spaced increments
per decade for DTH/MZP

(This listing is only generated
if XL = 1.0 in the CHOICES file
for this transfer function)

Exit PLOT

APPENDIX E

INTERCOM EXAMPLE PROBLEM

This appendix presents a typical terminal session in the Intercom 4.7 operating system, accessing the CSA mainframe at Wright-Patterson AFB's ASD Computer Center. The dialog is annotated so that a typical user will easily understand the basic sequences of parameter entry and job steps. All user responses are underlined; each is terminated by a carriage return.

This particular session was an exercise using a 9 cm viewing distance and the standard crewman (STDCRW) parameter set. It was one of a series of runs which attempted to determine optimal display distance for minimizing image motion of a vertically vibrating crewman. The example is carried far enough for the potential user to see how the programs interface with INTERCOM job control and file management commands.

The steps followed in the investigation are listed below:

- 1) Log in to Intercom.
- 2) Attach the PARAMETER file to be modified and name it TAPE20.
- 3) Attach the CREATE program, called EXECRT.
- 4) Run EXECRT, make changes to existing file, assemble new CHOICES file.
- 5) Assemble batch job to run BIODYN and PLOT, using the two PARAMETER file (old and modified) and the new CHOICES file.
- 6) Submit batch job to input queue.
- 7) When job completed, list the output file.

The user is advised to retain in his permanent files only those which he wishes to use in the future, and to frequently purge his directory of unneeded parameter and output files in order to forestall job failures resulting from file space overload.

Typical INTERCOM Terminal Session

user responses underlined

```
ASD COMPUTER CENTER INTERCOM 5.0
SYSTEM CSA
DATE 05/20/80      TIME 14.46.39.

PLEASE LOGIN

ENTER 3-DIGIT TERMINAL ID-
05/20/80  LOGGED IN AT 14.46.52.
          WITH USER-ID CA
          EQUIP/PORT 12/001

COMMAND- REQUEST,TAPE7,*PF
COMMAND- REQUEST,TAPE8,*PF
COMMAND- ATTACH,TAPE20,STDCRW

PF CYCLE NO. - 001

COMMAND- ATTACH,EXECRT

PFN IS
EXECRT
PF CYCLE NO. - 001
COMMAND- EXECRT
NEW FILE ?
NO LISTING DESIRED?
YE (LONG OR (SHORT LISTING?
LI (LONG OR (SHORT LISTING?
LO NEW CHOICES FILE ?
YE BIDDYN YES DESIRED FOR PIVIB ?
NO

TRANSFER FUNCTION INPUT :
FIRST LINE-RESPONSE MNEMONIC, FORCING FUNCTION MNEMONIC
(AAA,AAA) ; ENTER XXX TO STOP
SECOND LINE-PLOTTING INFORMATION, 5 ITEMS :
BODE LOWER FREQ. LIMIT
BODE UPPER FREQ. LIMIT
BODE UPPER PHASE LIMIT (0. DEFAULTS TO 200.)
BODE LOWER PHASE LIMIT (0. DEFAULTS TO -400.)
LIST (1. TO LIST TABLE, 0. FOR NO LIST)
IF NO PLOT DESIRED, ENTER 0. FOR ALL ITEMS
RHF,DZF
RHF NOT PERMISSIBLE, PLEASE REINPUT
RHD,DZF
1,200,0,0,1.
MAX FREQUENCY RANGE IS 3 DECADES
PLEASE REINPUT ENTIRE LINE
1,100,0,0,1.
XXX
STOP
.222 OF SECONDS EXECUTION TIME
```

1. Log in to INTERCOM

2. Attach files to I/O units

3. Attach EXECRT(CREATE) program file

4. Execute EXECRT program module

5. Select existing data file (STDCRW)

6. List data file

7. Program rejects unrecognizable input

8. Long listing option selected

9. Affirmative on CHOICES option

10. Negative on PIVIB option

11. Illegal parameter selected

12. Program screens for out-of-limit values

13. Finally, valid input

14. Exit from CREATE

Session continues with batch run

Sample INTERCOM Batch run

COMMAND- <u>EDITOR</u>	1. Invoke INTERCOM editor
<u>..CREATE,S</u>	
ENTER LINES	
<u>SAR,C4150000,STCSA, L800015,RIEDEL,(213)679-2281</u>	
<u>ATTACH,TAPE7,CHOICE1.</u>	
<u>ATTACH,TAPE8,VIEW9.</u>	
<u>ATTACH,EXEBIO.</u>	
<u>ATTACH,EXEPLT.</u>	
<u>EXEBIO(TAPE4,OUTPUT,TAPE7,TAPE8,TAPE19,TAPE21).</u>	
<u>REWIND,TAPE19.</u>	
<u>EXEPLT(OUTPUT,TAPE19).</u>	
<u>#FOR</u>	
<u>=</u>	
<u>..SAVE,GOFIL,NOSEQ</u>	
<u>..STORE,GOFIL,L800015</u>	
CT ID= L800015 PFN=GOFIL	
CT CY= 001 00000128 WORDS.:	
<u>..END</u>	
COMMAND- <u>BATCH,GOFIL,INPUT,HERE</u>	4. Batch job stream to input queue
COMMAND- FILES	
--LOCAL FILES--	
*EXECRT *GOFIL \$INPUT \$OUTPUT *TAPE7	
*TAPE8 *TAPE20	
--REMOTE EXECUTING JOBS--	
SARCK02	
COMMAND-	
TASK "S...TEL" TERMINATED	
TASK EXIT WITH OUTSTANDING IO	
PC=106646	
PS=170000	
RO=003770	5. Job terminated by system crash

Note: Output files generated by BIODYN, when listed, are identical in format to printouts shown in Appendix D.

REFERENCES

1. Jex, H. R., and R. E. Magdaleno, Modeling Biodynamic Effects of Vibration, Fifth Year; Final Scientific Report, Systems Technology, Inc., SR-1037-1, Aug. 1979.
2. Jex, H. R., and R. E. Magdaleno, "Progress in Measuring and Modeling the Effects of Low Frequency Vibration on Performance," Models and Analogues for the Evaluation of Human Biodynamic Response, Performance and Protection, AGARD CP-253, June 1979, pp. A29-1 through A29-11.
3. Jex, H. R., and R. E. Magdaleno, "Biomechanical Models for Vibration Feedthrough to Hands and Head for a Semisupine Pilot," Aviation, Space and Environmental Med., Vol. 49, No. 1, Jan. 1978, pp. 304-316.
4. Magdaleno, R. E., and H. R. Jex, User's Guide to BIODYN-78, An Interactive Computer Program for Modeling Biodynamic Feedthrough to a Pilot's Hands and Head, Systems Technology, Inc., TR-1037-2, July 1979.
5. Jex, H. R., and R. W. Allen, "Evaluating Biodynamic Interference with Operational Crews," Vibration and Combined Stresses in Advanced Systems, AGARD CP-145, Mar. 1975, pp. B24-1 through B24-18.
6. Jex, H. R., and R. E. Magdaleno, Modeling Biodynamic Effects of Vibration; Fourth Year Interim Scientific Report, Systems Technology, Inc., ISR-1037-4, Sept. 1978.
7. Berliner, Jeffrey E., and William H. Levison, PIVIB: A Computer Program for Analysis of Pilot Biodynamic and Tracking Response to Vibration, Bolt, Beranek and Newman, Rept. 3457, Dec. 1976.
8. ASD Computer Center CDC NOS/BE User's Guide, Rev. E, Jan. 1978.
9. ASD Computer Center INTERCOM Guide, Rev. A, Sept. 1976.
10. Magdaleno, R. E., D. T. McRuer, and G. P. Moore, Small Perturbation Dynamics of the Neuromuscular System in Tracking Tasks, NASA CR-1212, Dec. 1968.
11. Braune, W., O. Fischer, J. Amar, and W. T. Dempster, Human Mechanics; Four Monographs Abridged, AMRL-TDR-63-123, Dec. 1963. (AD 600618)
12. "Symposium on Biodynamic Models and Their Applications," Dayton, Ohio, 15-17 Feb. 1977, published in Av., Space and Environ. Med., Vol. 49, No. 1, Jan. 1978.

END

DATE
FILMED

10-81

DTIC